

LJ-V7000 Series LabVIEW measuring instrument drivers Reference Manual

Contents 4. Installation Steps......4 5. How to Use Instrument Drivers......5 6. Instrument Drivers Package......5 9.2 Details of Items for Sending/Receiving Settings.......18 9.2.3.11 Measurement Area details.......41 9.3 Write processing for settings.......45 10.1 Internal memory of controller......47 10.2 Profile data amount calculation method.......48 10.5 Storage Order of Profile Storage Data and Specific Examples......52 10.6 Storage Order of Batch Profile Storage Data and Specific Examples......52 10.7 Storage Order of Data Storage Data and Specific Examples......53

1. Software License Agreement

NOTICE TO USER: PLEASE READ THIS SOFTWARE LICENSE AGREEMENT (THIS "AGREEMENT") CAREFULLY. BY USING ALL OR ANY PORTION OF THIS "SOFTWARE", YOU ARE AGREEING TO BE BOUND BY ALL THE TERMS AND CONDITIONS OF THIS AGREEMENT. IF YOU DO NOT AGREE TO ANY TERMS OF THIS AGREEMENT, DO NOT USE THIS SOFTWARE.

1. Grant of License.

Conditioned upon compliance with all of the terms and conditions of this Agreement, KEYENCE grants you a nonexclusive and nontransferable license.

2. Restrictions

Except for installation of updates or new functions provided by KEYENCE, you may not modify or add any function to this Software.

- a) You may not reverse engineer, decompile or disassemble this Software.
- b) You may not create derivative works based on this Software.
- c) Other than expressly stated by KEYENCE, you may not resell, retransfer, rent or otherwise redistribute this Software to any third parties. However, you may redistribute this Software with the application that you developed using this Software.

3. Intellectual Property Rights.

Except as expressly stated herein, KEYENCE reserves all right, title and interest in this Software, and all associated copyrights, trademarks, and other intellectual property rights therein.

4. Disclaimer.

Keyence is licensing this Software to you "AS IS" and without any warranty of any kind. In no event will KEYENCE or its suppliers be liable to you for any damages, claims, costs or any lost profits caused by using this Software.

5. Support

KEYNCE shall not provide technical support in accordance with this Software including the use of this Software.

6. Termination.

- 6.1 Your license under this Agreement will terminate automatically if you destroy this Software and the copy of this Software in your possession or voluntarily return this Software to us.
- 6.2 Your license under this Agreement will terminate automatically without any notice from KEYENCE if you fail to comply with any of the terms and conditions of this Agreement. Promptly upon termination, you shall cease all use of this Software and destroy all copies, full or partial, of this Software in your possession or control.
- 6.3 You will compensate KEYENCE for costs or any lost profits caused by your violation or breach of any term of this Agreement.

7. Governing Law.

This Agreement will be governed by and construed in accordance with the substantive laws of Japan without regards to the principles of conflicts of law.

2. Introduction

The LJ-V7000 Series LabVIEW measuring instrument drivers provides a communication interface for controlling the LJ-V7000

The drivers have been created based on the LabVIEW standard plug-and-play measuring instrument driver template, which allows selection of VI from the LabVIEW function pallet (instrument I/O), in a similar way to many other plug-and-play measuring instrument drivers.

3. Operating Environment

The following operating environment and National Instruments LabVIEW 8.6 or later (32 bit) are required to use the LJ-V7000 Series LabVIEW measuring instrument drivers. In addition, LJ-Navigator2 needs to be installed.

| os | Windows 7 (Home Premium/Professional/Ultimate) Windows Vista (Home Basic/Home Premium/Business/Ultimate) Windows XP (SP2 or later) (Home Edition/Professional Edition) |
|------------------------|--|
| CPU | Core i3 2.3 GHz or faster (Core2 Duo 2.8 GHz or faster) |
| Memory | 2 GB or more |
| Secondary cache memory | 2 MB or more |
| Free drive space | 10 GB or more |
| Interface | A PC equipped with either of the interfaces below. USB 2.0/1.1 *1, Ethernet 1000BASE-T/100BASE-TX *2 |

^{*1} Operation is not guaranteed with connections via a USB hub

4. Installation Steps

Follow the installation steps described below to install the LJ-V7000 Series LabVIEW measuring instrument driver.

- (1) Copy the entire folder containing "Keyence LJ-V7000" to the instr.lib folder of LabVIEW. Location of the instr.lib folder Example: C:\(\text{Program Files}(x86)\)\(\text{YNational Instruments}\)\(\text{LabVIEW 2012}\)\(\text{Yinstr.lib}\)
- (2) Click Tools > Advanced > Mass Compile in LabView.
- (3) Select the "Keyence LJ-V7000" folder copied to instr.lib in "Select a directory to be compiled" and click the "Current folder".
- (4) Click "Mass compile".
 - * Bad VI: When the warning message "Keyence LJ-V7000.lvlib: VI Tree.vi" occurs, click "Done".
- (5) Copy the error code file (Keyence_LJ-V7000-errors.txt) to the errors folder in the LabVIEW user.lib folder. Location of the errors folder

Example: C:\Program Files\National Instruments\LabVIEW 2012\u00e4user.lib

* If there is no errors folder, create an errors folder within the above-mentioned user.lib folder and copy the error code file into it.

This completes the installation. However, you need to restart LabVIEW in order to use it.

* To uninstall LabVIEW, delete the file copied to the instr.lib folder in step (2) and the file copied to the user.lib folder in step (5) above.

^{*2} Operation is not guaranteed with connections to a LAN or via a router

5. How to Use Instrument Drivers

Select View > Functions Palette >Instrument I/O > Instr Drivers > "Keyence LJV7000" to select driver VI or sample VI. For specific ways to use the communication library, refer to the sample VI.

<Overvier of sample VI>

A: Read Measurement Data



→ Obtain the measurement results in Advanced mode

B: Read Profiles(for High-Speed Mode)




→ Read profiles in High speed mode with batch turned OFF

C: Read Batch Profiles(for High-Speed Mode)



→Read profiles in High speed mode with batch turned ON

D : Read Profiles(for High-Speed Data Communication)





E: Configure



→Send/receive settings

6. Instrument Drivers Package

This section provides a brief description of each of the VI instrument drivers. For more information, refer to Context Help in the VI file.

Items used in Sample VI A – E are marked with a circle in the right hand boxes.

| loon | VI name | Description of VI | Sample VI | | | | | | | |
|------------------------|-------------------------|---|-----------|---|---|---|---|--|--|--|
| Icon | Virianie | Description of VI | Α | В | С | D | Е | | | |
| KEYLUV7 VI TREE | VI tree | Display all the user-callable VIs of the instrument driver in an organized table. | | | | | | | | |
| KEYLUV7 | Initialize | Communication with the controller is established. | 0 | 0 | 0 | 0 | 0 | | | |
| KEYLJV7 | Close | Communication with the controller is terminated. | 0 | 0 | 0 | 0 | 0 | | | |
| KEYLJU7 C REBOOT | Reboot Controller | This function reboots the controller and connected devices. | | | | | | | | |
| KEYLUV7 | Return to Factory State | This function returns all of the controller's settings to the factory state. | | | | | | | | |
| ? Q ERROR? | Get System Error | This function gets the controller's system error information. | | | | | | | | |
| CLEAR | Clear System Error | This function clears the system error occurring on the controller. | | | | | | | | |
| KEYLJV7 → L TRG | Trigger | This function issues a trigger. | | | | | | | | |

^{*} For more information on sample VI, refer to Chapter 8.

| KEYLUV7 | Start Batch | This function starts batch measurements. | | | 0 | |
|------------------------------|--|---|---|---|---|---|
| ВАТСН | Measurements | This function starts batter measurements. | | |) | |
| KEYLJV7 | Stop Batch Measurements | This function stops batch measurements. | | | 0 | |
| EEVLJU7 ZERO | Auto Zero | This function issues an auto zero request. | | | | |
| KEYLJV7 TIM | Timing | This function issues a timing request. | | | | |
| RESET | Reset | This function issues a reset request. | | | | |
| KEYLJU7 | Set Setting | This function sends the setting for the specified item to the controller. | | | | 0 |
| KEYLJV7 S⇒ L→ 🏠 | Get Setting | This function gets the setting for the specified item by Target Setting from the controller. | | | | 0 |
| KEVLOV7 | Initialize Setting | This function initializes the setting specified by Target as the initialization target. | | | | |
| KEYLJV7 | Reflect Setting | This function reflects the settings stored in the write settings area to the running settings area. | | | | 0 |
| XEYLJU7 | Update Write Settings Area | This function updates the contents of the write settings area with either the settings in the running settings area or the settings saved in the save area. | | | | 0 |
| ? | Check Status of Saving to Save Area | This function checks whether or not the controller is accessing the save area with an operation such as that to save settings. | | | | 0 |
| KEYLJV7 S— O 📭 | Set Time | This function sets the date/time for the controller. | | | | |
| KEYLUV7 Ə⇒ ➡ © | Get Time | This function gets the date/time from the controller. | | | | |
| KEYLJV7 SP PROC No. | Change Program | This function changes the active program number. | | | | |
| KEYLJU7 PROC | Get Active Program Number | This function gets the date/time from the controller. | | | | |
| KEYLJU7 | Read Measurement Data | This function gets the newest measurement results (measurement values and judgment results). | 0 | | | |
| KEYLJV7 GG | Read Profiles(for High-Speed Mode) | This function gets profile data when the operation mode is "high-speed" *1, *2 | | 0 | | |
| KEYLUV? | Read Batch Profiles(for High-Speed Mode) | This function gets profile data when the operation mode is "high-speed" and Batch measurement: on. *If Compression (time axis) is ON, use Read Profiles (for High-Speed Mode) VI. *1, *2 | | | 0 | |
| KEYLJV7 | Read Profiles(for Advanced Mode) | This function gets profile data when the operation mode is "Advanced(with OUT measurement)" *1 | | | | |

| 1 | | | | | | |
|--|---|---|--|---|---|--|
| Read Batch Profiles(for Advanced Mode) | This function gets profile data when the operation mode is "Advanced (with OUT measurement)" and Batch measurement: on. *If Compression (time axis) is ON, use Read | | | | | |
| | 1 | | | | | |
| Extract-Header-Data-Arr ay | Only various data composing headers will be extracted to output in one dimensional array from profile data acquired with Read Profiles VI. | | | | | |
| Extract-Profile-Array | Only height data of profiles without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. | | 0 | 0 | 0 | |
| Start Storage | When the storage condition setting is terminal/command, this function requests the start of storage. | | | | | |
| Stop Storage | When the storage condition setting is terminal/command, this function requests the stop (cancellation) of storage. | | | | | |
| Read Storage Status | When the storage target setting is not off, this function gets the storage status. *2 | | | | | |
| Read Data Storage Data | Storage data will be acquired if "storage target" is set to "OUT value". *2, *3 | | | | | |
| Clear Memory | When the operation mode is "high-speed (profile only)", this function clears the profile data accumulated in internal memory. When the operation mode is "advanced (with OUT measurement)", the accumulated storage data is cleared. | | | | | |
| Read Profile Storage Data | When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 | | | | | |
| Read Batch Profile Storage Data | When the storage target setting is profile, this function gets the stored profile data. (Batch setting: on) *If Compression (time axis) is ON, use Read ProfileStorage Data VI. *1, *2, *3 | | | | | |
| Start High-Speed Data Communication | High-speed communication with the controller is established to start. | | | | 0 | |
| Stop High-Speed Data Communication | High-speed data communication will be terminated. | | | | 0 | |
| Read Profiles(for High-Speed Data Communication) | Profile data will be acquired by high-speed communication. *1 | | | | 0 | |
| | Extract-Header-Data-Arr ay Extract-Profile-Array Start Storage Read Storage Status Read Data Storage Data Clear Memory Read Profile Storage Data Read Batch Profile Storage Data Start High-Speed Data Communication Stop High-Speed Data Communication Read Profiles(for High-Speed Data | Read Batch Profiles(for Advanced Mode) Read Batch Profiles(for Advanced Mode) Extract-Header-Data-Arr ay Extract-Profile-Array Extract-Profile-Array Common Storage Read Storage Status Read Data Storage Data Clear Memory Clear Memory Read Profile Storage Data Read Profile Storage Read Batch Profile Storage Data Read Batch Profile Read Batch Profile Storage Data Read Batch Profile Storage Data Operation mode is "Advanced (with OUT measurement)" and Batch measurement: on. "If Compression (time axis) is ON, use Read Profiles (for Advanced Mode) VI. "1 Only various data composing headers will be extracted to output in only only neight data acquired with Read Profiles VI. Only height data of profiles without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. When the storage condition setting is terminal/command, this function requests the story (cancellation) of storage. When the storage target setting is not off, this function gets the storage status. *2 Storage data will be acquired if "storage target" is set to "OUT value". *2, *3 When the operation mode is "high-speed (profile only)", this function clears the profile data accumulated in internal memory. When the operation mode is "advanced (with OUT measurement)", the accumulated storage data is cleared. When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 When the storage target setting is profile, this function gets the stored profile data. (Batch setting: on) "If Compression (time axis) is ON, use Read ProfileStorage Data VI. *1, *2, *3 Start High-Speed Data Communication Read Profiles(for High-Speed Data Communication Read Profiles(for High-Speed Data Communication Profile data will be acquired by high-speed communication. *1 | Read Batch Profiles(for Advanced Mode) Read Batch Profiles(for Advanced Mode) Extract-Header-Data-Arr ay Extract-Profile-Array Only various data composing headers will be extracted to output in one dimensional array from profile data acquired with Read Profiles VI. Only height data of profiles without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. When the storage condition setting is terminal/command, this function requests the start of storage. When the storage condition setting is terminal/command, this function requests the storage cancellation) of storage. Read Storage Status Read Data Storage Data Read Profile Storage Clear Memory Clear Memory Read Profile Storage Data Read Batch Profile Storage Data Read Batch Profile Storage Data Read Batch Profile Storage Data Read Batch Profile Storage Data When the storage target setting is profile, this function gets the storage target setting is profile, this function gets the storage target setting is profile, this function gets the storage target setting is profile, this function gets the storage target setting is profile, this function gets the storage target setting is profile, this function gets the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 Start High-Speed Data Communication Read ProfileStorage Data VI. *1, *2, *3 High-speed data communication will be terminated. Read Profiles(for High-Speed Data communication *1 Profile data will be acquired by high-speed communication *1 | Read Batch Profiles(for Advanced Mode) Pofiles(for Advanced Mode) Profiles(for Advanced Mode) Profiles(for Advanced Mode) Profiles(for Advanced Mode) Only various data composing headers will be extract-Header-Data-Arr ay Extract-Header-Data-Arr ay Only height data of profiles without a header and footer will be extracted to output in one dimensional array from profile data acquired with Read Profiles VI. Only height data of profiles without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. When the storage condition setting is terminal/command, this function requests the start of storage. When the storage condition setting is terminal/command, this function requests the stop (cancellation) of storage. When the storage status without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. When the storage condition setting is terminal/command, this function requests the storage cancellation) of storage. When the storage target setting is not off, this function gets the storage status. *2 Storage data will be acquired if "storage target" is set to "OUT value". *2, *3 When the operation mode is "high-speed (profile only)", this function clears the profile data accumulated in internal memory. When the operation mode is "advanced (with OUT measurement)", the accumulated storage data is cleared. When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) *1, *2, *3 Start High-Speed Data Communication High-speed communication with the controller is established to start. High-speed data communication will be terminated. Read Profiles(for High-Speed Data Communication Profile data will be acquired by high-speed communication will be terminated. | Read Batch Profiles(for Advanced Mode) operation mode is "Advanced (with OUT measurement)" and Batch measurement: on. "If Compression (time axis) is ON, use Read Profiles(for Advanced Mode) VI. "1 Only various data composing headers will be extracted to output in one dimensional array from profile data acquired with Read Profiles VI. Only height data of profiles without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. When the storage condition setting is terminal/command, this function requests the start of storage. When the storage condition setting is terminal/command, this function requests the stop (cancellation) of storage. Read Storage Status Read Data Storage Data When the storage target setting is not off, this function gets the storage target setting is not off, this function gets the storage target setting is not off, this function gets the storage target setting is not off, this function gets the storage target setting is not off, this function gets the storage target setting is profile data accumulated in internal memory. When the operation mode is "high-speed (profile only)", this function clears the profile data accumulated in internal memory. When the operation mode is "advanced (with OUT measurement)", the accumulated storage data is cleared. Read Profile Storage When the storage target setting is profile, this function gets the stored profile data. (Batch setting: on) "If Compression (time axis) is ON, use Read ProfileStorage Data VI. *1, *2, *3 Start High-Speed Data Communication Read Profiles(for High-Speed Communication with the controller is established to start. High-speed data communication will be terminated. | peration mode is "Advanced (with OUT measurement)" and Batch measurement: on. "If Compression (time axis) is ON, use Read Profiles (for Advanced Mode) VI. 1 Only various data composing headers will be extracted to output in one dimensional array from profile data acquired with Read Profiles VI. Only height data of profiles without a header and footer will be extracted to output in two-dimensional array from profile data acquired with Read Profiles VI. When the storage condition setting is terminal/command, this function requests the start of storage. When the storage condition setting is terminal/command, this function requests the stop (cancellation) of storage. Read Storage Status Read Data Storage Data When the storage target setting is not off, this function gets the storage target setting: snot off, this function of storage target setting is not off, this function of storage target setting is not off, this function gets the storage target setting is profile data accumulated in internal memory. When the operation mode is "high-speed (profile only", this function nedes the profile data accumulated in internal memory. When the operation mode is "advanced (with OUT measurement)", the accumulated storage data is cleared. When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) "1, "2, "3 When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) "1, "2, "3 When the storage target setting is profile, this function gets the stored profile data. (Batch setting: off) "1, "2, "3 Start High-Speed Data Communication Read Profiles(for High-Speed data communication with the controller is established to start. Profile data will be acquired by high-speed communication "1 Oncommunication 1 |

^{*1} Refer to sections 10.2 Profile DataAmount Calculation Method and 10.3 Profile Data Storage Order and Specific Examples for use.

^{*2} Refer to sections 10.1 Internal Memory of Controller for use.

 $^{^{\}star}3$ Refer to sections 10.3 - 10.5 Profile Data Storage Order and Specific Examples for use.

7. Error code

The error codes below show a table of error codes and source text that each driver VI outputs to the **error out** output terminal.

These error codes are output according to the judgment of driver VI.

| Code | Description of error |
|------|---|
| 5000 | Failed to open the communication path. |
| 5001 | The communication path was not established. |
| 5002 | Failed to send the command. |
| 5003 | Failed to receive a response. |
| 5004 | A timeout occurred while waiting for the response. |
| 5005 | Failed to allocate memory. |
| 5006 | An invalid parameter was passed. |
| 5007 | The received response data was invalid. |
| 5009 | High-speed communication initialization could not be performed. |
| 5010 | High-speed communication was initialized. |
| 5011 | Error already occurred during high-speed communication (for high-speed communication) |
| 5012 | The buffer size passed as an input of the VI is insufficient. |

Error codes returned from the controller and output by driver VI. These errors are output if the controller failed to process even though communication with the controller was successful.

| Code | Description of error |
|------|---|
| 6000 | Status error (when a system error has occurred, etc.) |
| 6001 | Parameter error (when an invalid parameter was set, etc.) |

Other individual VI error codes.

| Code | Description of error |
|------|---|
| 6500 | The trigger mode is not "external trigger" |
| 6501 | Batch measurements are off |
| 6502 | The change program setting is "terminal" |
| 6503 | The operation mode is "high-speed (profile only)" |
| 6504 | The operation mode is "advanced (with OUT measurement)" |
| 6505 | "Batch measurements on and profile compression (time axis) off" |
| 6506 | Not "batch measurements on and profile compression (time axis) off" |
| 6507 | Storage target setting is "OFF" (no storage) |
| 6508 | The storage condition setting is not "terminal/command" |
| 6509 | The storage target setting is <u>not</u> "OUT value" |
| 6510 | The storage target setting is <u>not</u> profile, or "batch measurements on and profile compression |
| 0310 | (time axis) off" |
| 6511 | The storage target setting is <u>not</u> profile, or <u>not</u> "batch measurements on and profile |
| 0311 | compression (time axis) off" |
| 6512 | The data specified as the send start position does not exist |
| 6700 | Accessing the save area |
| 6701 | Batch measurement start/stop processing could not be performed because the REMOTE |
| 0701 | terminal is off or the LASER_OFF terminal is on |
| 6702 | No profile data |
| 6703 | No batch data (batch measurements not run even once) |
| 6704 | The batch data specified by the batch number to read (Read Batch No) in Read Req has not |
| 0704 | been accumulated yet |
| 6705 | Already performing high-speed data communication |
| 6800 | The VI has never received the profile data in the high-speed communication within a specified |
| 0000 | time out frame. |
| 6801 | The buffer size passed as an input is insufficient. |
| 6802 | High-speed communication has never been started. |
| 6803 | Parameter error |
| 6815 | System error |

<Table listing individual error codes and VIs>

| VI name | 6500 | 6501 | 6502 | 6503 | 6504 | 6505 | 6506 | 6507 | 6508 | 6509 | 6510 | 6511 | 6512 |
|--|------|------|------|------|------|------|------|------|------|------|------|------|------|
| Trigger | 0 | | | | | | | | | | | | |
| Start Batch Measurements | | 0 | | | | | | | | | | | |
| Stop Batch Measurements | | 0 | | | | | | | | | | | |
| Auto Zero | | | | 0 | | | | | | | | | |
| Timing | | | | 0 | | | | | | | | | |
| Reset | | | | 0 | | | | | | | | | |
| Change Program | | | 0 | | | | | | | | | | |
| Read Measurement Data | | | | 0 | | | | | | | | | |
| Read Profiles(for High-Speed Mode) | | | | | 0 | 0 | | | | | | | |
| Read Batch Profiles(for High-Speed Mode) | | | | | 0 | | 0 | | | | | | |
| Read Profiles(for Advanced Mode) | | | | 0 | | 0 | | | | | | | |
| Read Batch Profiles(for Advanced Mode) | | | | 0 | | | 0 | | | | | | |
| Start Storage | | | | 0 | | | | 0 | 0 | | | | |
| Stop Storage | | | | 0 | | | | 0 | 0 | | | | |
| Read Storage Status | | | | 0 | | | | | | | | | |
| Read Data Storage Data | | | | 0 | | | | | | 0 | | | |
| Read Profile Storage Data | | | | 0 | | | | | | | 0 | | |
| Read Batch Profile Storage Data | | | | 0 | | | | | | | | 0 | |
| Start High-Speed Data Communication | | | | | 0 | | | | | | | | 0 |
| Read Profiles(for High-Speed Data Communication) | | | | | 0 | | | | | | | | |


| VI name | 6700 | 6701 | 6702 | 6703 | 6704 | 6705 | 6800 | 6801 | 6802 | 6803 | 6815 |
|--|------|------|------|------|------|------|------|------|------|------|------|
| Reboot Controller | 0 | | | | | | | | | | |
| Start Batch Measurements | | 0 | | | | | | | | | |
| Stop Batch Measurements | | 0 | | | | | | | | | |
| Read Profiles(for High-Speed Mode) | | | 0 | | | | | | | | |
| Read Batch Profiles(for High-Speed Mode) | | | | 0 | | | | | | | |
| Read Profiles(for Advanced Mode) | | | 0 | | | | | | | | |
| Read Batch Profiles(for Advanced Mode) | | | | 0 | | | | | | | |
| Read Batch Profile Storage Data | | | | | 0 | | | | | | |
| Start High-Speed Data Communication | | | | | | 0 | | | | | |
| Read Profiles(for High-Speed Data Communication) | | | | | | | 0 | 0 | 0 | 0 | 0 |

8.Sample VII

This section describes each Sample VI.

A: Read Measurement Data


→Read the measurements in Advanced mode. When Sample VI is run, real time measurements are displayed.



| 1 | Select communication | Select either USB or Ethernet. |
|---|------------------------|--|
| | path | |
| 2 | Ethernet communication | Specify the IP address and port number. |
| | setting | |
| 3 | VI Stop button | Stops VI. |
| 4 | Select Display OUT | Displays measurements and evaluation results (HI, GO, LO). Measure Data |
| | | output array of the Read Measurement Data VI is displayed unchanged as an |
| | | indicator. To change the range of OUT to be displayed, change the value of |
| | | the index number within the range 0 to 15. |

B : Read Profiles(for High-Speed Mode)


 \rightarrow Read profiles in High speed mode with batch turned OFF.



| 1 | Select communication path | Select either USB or Ethernet. |
|-----|-----------------------------|---|
| 2 | Ethernet communication | Specify the IP address and port number. |
| | setting | |
| 3 | VI Stop button | Stops VI. |
| 4 | Input to Read Profile | Specify conditions for reading profiles. Read Req input to be connected to |
| | Request | Read Profiles (for High-Speed Mode) VI input terminal is displayed as a |
| | | control. (By default, the latest profile is read from the active surface, and |
| | | the profile read is set so that it is not cleared from the controller.) |
| (5) | Profile Information Display | Profile Info output of Read Profiles (for High-Speed Mode) VI is |
| | | displayed unchanged as a indicator. |
| 6 | Profile Response Display | Profile Rsp output of Read Profiles (for High-Speed Mode)is displayed |
| | | unchanged as a indicator. |
| 7 | Profile Monitor | Profiles are presented in a graph display. |
| | (XY graph) | Vertical and horizontal axes are expressed in mm units. |

C: Read Batch Profiles(for High-Speed Mode)


 \rightarrow Read profiles in High speed mode with batch ON.



| 1 | Select communication path | Select either USB or Ethernet. |
|----------|-----------------------------|---|
| 2 | Ethernet communication | Specify the IP address and port number. |
| | setting | |
| 3 | VI Stop button | Stops VI. |
| 4 | Batch Point | Specify the number of batch points to be read. |
| ⑤ | Input to Read Profile | Specify conditions for reading profiles. Read Req input to be connected to |
| | Request | Read Batch Profiles (for High-Speed Mode) VI input terminal is |
| | | displayed as a control. |
| 6 | Profile Information Display | Profile Info output of Read Profiles (for High-Speed Mode) VI is |
| | | displayed unchanged as an indicator. |
| 7 | Profile Response Display | Profile Rsp of Read Profiles (for High-Speed Mode) VI is displayed |
| | | unchanged as an indicator. |
| 8 | Height Image Monitor | The batch profile read by batch profile reading is displayed as the height |
| | Display | image. |
| | | The horizontal axis represents the X-coordinate. (It is expressed in the unit |
| | | data quantity, not mm.) |
| | | The vertical axis represents the batch point orientation. |
| | | The Z-axis (height direction of LJV) is shown on a gray scale. (Example: It |
| | | indicates that the white area is high while the black area is low.) |
| 9 | Monitor Start button | Reads batch data from the controller. |
| | | (When reading batch data finishes, VI stops.) |
| 10 | Batch Start/Stop button | Starts/stops batch measurement. |

D: Read Profiles(for High-Speed Data Communication)

 \rightarrow Reads profiles in High speed mode via high speed communication.




| 1 | Select communication path | Select either USB or Ethernet. |
|----------|--------------------------------|---|
| 2 | Ethernet communication setting | Specify the IP address and port number. |
| 3 | Port number for high speed | When communications are carried out over Ethernet, specify a port |
| | communication | number for high-speed communication set for the controller. |
| | | * Specify a port number that is different from the one specified in (2). |
| 4 | VI Stop button | Stops VI. |
| ⑤ | Input to High Speed | Specify conditions for high-speed communications. Start Req input |
| | Communication Request | connected to the input terminal of Start High-Speed Data |
| | | Communication VI is displayed unchanged as a control. |
| 6 | Notify Output | Notify output of Start High-Speed Data Communication VI is |
| | | displayed unchanged as a control. |
| 7 | Number of Profiles Read | Indicates how many profiles have been read after profile reading is |
| | | started in (13). The number of profiles specified in Rsp Profile Cnt |
| | | in (5) x the number of profiles read in (7) equals the number of |
| | | profiles that were actually read. |
| 8 | Total Timeout Count Output | When a request for reading profiles is made in (13) and the number |
| | | of profiles specified in Read Profile Cnt in (5) cannot be read in one |
| | | second, a timeout error occurs. This number is counted. Example: |
| | | When profiles are read in (13), but high-speed communications in |
| | | (12) are not carried out, or when high-speed communications in (12) |
| | | are carried out but the specified number of profiles are not updated |
| | | (no trigger input or slow sampling frequency), a time error occurs. |
| 9 | Buffer usage | The Buf Usage Rate output of Read Profiles (for High-Speed Data |
| | | Communication) VI is displayed. Profiles are stored by (12) in the |
| | | buffer provided on your computer. The buffer usage rate is displayed |
| | | in %. Once a profile is read by (13), the read profile is cleared from |
| | | within the buffer. If the buffer usage rate is 100%, the number of |
| | | profiles stored in (12) exceeds the number of profiles read in (13), |
| | | indicating that profiles are not stored at each sampling frequency. |
| | | |

| 10 | Profile Information Display | Profile Info output of Read Profiles (for High-Speed Data |
|-----|--------------------------------|---|
| | | Communication) VI is displayed unchanged as a indicator. |
| 11) | Height Image Monitor Display | Displays a profile as a height image. The horizontal axis represents |
| | | the number of profiles. The vertical axis represents the X-coordinate |
| | | of LJV. (It is expressed in the unit data quantity, not mm.) |
| | | Indicates the Z-axis (height direction of LJV) on a gray scale. |
| | | (Example: It indicates that the white area is high while the black area |
| | | is low.) |
| 12 | High Speed Data Communication | Starts/stops high-speed communication between LJV and PC. |
| | Start/Stop Button | (Profiles are stored in the buffer provided on a PC/storage stops.) |
| 13 | Profile Read Stop/Start Button | Reads profiles stored in the PC in (12), and stops/starts the height |
| | | image display. |

E : Configure

→Sends/receives settings (For more information on how to send/receive settings, refer to Chapter 9.)



| 1 | Select communication path | Select either USB or Ethernet. |
|---|--------------------------------|---|
| 2 | Ethernet communication setting | Specify the IP address and port number. |
| 3 | VI Stop Button | Stops VI. |
| 4 | Send/Receive Settings Button | Sends/receives the set items. |
| 5 | Area for Sending/Receiving | Specify an area for sending/receiving settings. For more information, |
| | Settings | refer to 9.3 "Writing Processing for Settings". |
| 6 | Setting Items | Inputs/outputs setting items. For more information, refer to 9.1 |
| | | "Sending/Receiving Settings". |
| 7 | Update Writing Area | Settings in the Writing Area are reflected in the RUNNING AREA or |
| | | SAVE AREA. For more information, refer to 9.3 "Writing Processing |
| | | for Settings". |
| 8 | Updating the WRITE AREA | Used to return settings in the WRITE AREA that are not consistent |
| | | with the settings within the controller. For more information, refer to |
| | | 9.3 "Writing Processing for Settings". |
| 9 | Saving Operation & Error Check | Displays errors that occurred during sending/receiving of settings. |
| | | While writing settings to the SAVE AREA, Accessing the SAVE area |
| | | lights green. |

9. How to Send/Receive Settings

9.1. Sending/Receiving Settings

The LJ-V7000 Series can send/receive settings for each item using **Set Setting** VI and **Get Setting** VI. This section explains **Target Setting** and **Setting Data** that are input to Set Setting and Get Setting VIs.(For information on **Setting Depth**, refer to 9.3 "Write Processing for Settings".)

Target Setting: Specify items for sending/receiving settings. Members are as shown below. For detailed parameters of each member, refer to 9.2 Details of Items for Sending/Receiving Settings.

| Туре | Specify which settings of the Environmental settings, Common measurement settings or Program 0 - Program 15 should be sent/received. |
|----------|--|
| Category | When sending or receiving settings for Program 0 - Program 15, specify which settings should be sent/received as Trigger settings and Imaging settings. When sending or receiving Environment settings or Measurement common settings, specify 0. |
| Item | Specify which settings of the items specified in Category should be sent/received. |
| Target1 | It is necessary to specify these items according to the send/receive |
| Target2 | settings. If settings are not required, specify 0. |
| Target3 | |
| Target4 | |

Setting Data: Specify the setting data to send/receive settings. For more information, refer to 9.2 "Details of Items for Sending/Receiving Settings".

9.2 Details of Items for Sending/Receiving Settings

9.2.1 Changing Environmental Settings

<Device name>

Type:01h, Category:00h, Item:00h

Target1~4:00h

| byte | Setting Data |
|------|----------------------|
| 0 | Device name, byte 1 |
| 1 | Device name, byte 2 |
| 2 | Device name, byte 3 |
| to | to |
| 31 | Device name, byte 32 |

^{*32} characters max. 0 is not appended to the end.

<Operation at next power on>

Type:01h, Category:00h, Item:01h

Target1~4:00h

| byte | Setting Data |
|------|-----------------------------|
| | Operation at next power on |
| 0 | 0:BOOT→IP addresses fixed, |
| | 1:IP address fixed, 2:BOOTP |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<High-speed communication band restriction>

Type:01h, Category:00h, Item:02h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | High-speed communication bandrestriction |
| | 0:OFF, 1:500Mbps, 2:200Mbps, 3:100Mbps |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<MTU during high-speed communication>

Type:01h, Category:00h, Item:03h

Target1~4:00h

| byte | Setting Data |
|------|-----------------------|
| 0 | MTU setting∶1500~9216 |
| 1 | |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<IPaddress/Subnet mask/Gateway>

Type:01h, Category:00h

Item:04h(IP address)/05h(Subnet mask)

/06h (Gateway)

Target1~4:00h

| byte | Setting Data |
|------|----------------------------------|
| 0 | IP address、1 st byte |
| 1 | IP address, 2 nd byte |
| 2 | IP address, 3 rd byte |
| 3 | IP address、4 th byte |

The following IP addresses are treated as invalid IP addresses:

 $0.0.0.0./224.0.0.0 \sim 255.255.255.255$

The following addresses are treated as invalid subnet masks:

0.0.0.0/255.255.255.255/ There are no consecutive[1]bits from

11.01000000 is an error)

The following addresses are treated as invalid gateway:

224.0.0.0~255.255.255.255

<TCP command port number/TCP high-speed port number >

Type:01h, Category:00h

Item:07h(TCP command port number)/08h(TCP high-speed port)

Target1~4:00h

| byte | Setting Data |
|------|------------------------|
| 0 | Dort pumber(4 - CFF2F) |
| 1 | Port number(1~65535) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

Do not set TCP command ports number same as TCP

high-speed port number.

<Baud rate>

Type:01h, Category:00h, Item:0Ah

| byte | Setting Data |
|------|---|
| 0 | Baud rate: |
| | 0:9600、1:19200、2:38400、3:57600、4:115200 |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Parity>

Type:01h, Category:00h, Item:0Bh

Target1~4:00h

| byte | Setting Data |
|------|----------------------------|
| 0 | Parity:0:NONE、1:EVEN、2:ODD |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

9.2.2 Common measurement settings

<Operation mode>

Type:02h, Category:00h, Item:00h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Operation mode: 0:High-speed, 1:Advanced |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Memory allocation>

Type:02h, Category:00h, Item:01h

Target1~4:00h

| byte | Setting Data |
|------|--|
| | Memory allocation setting: 0:Double buffer, 1:Entire |
| 0 | area(overwrite), 2:Entire area(do not overwrite) |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Operation when memory full>

Type:02h, Category:00h, Item:02h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Operation when memory full: 0:Overwrite, 1:Stop |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Parallel imaging>

Type:02h, Category:00h, Item:03h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Parallel imaging: 0: Disabled, 1: Enabled |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Strobe output time>

Type:02h, Category:00h, Item:04h

Target1~4:00h

| byte | Setting Data |
|------|--|
| | Strobe output time: 0:10µs, 1:20µs, 2:50µs, 3: |
| 0 | 100μs、4:200μs、5:500μs、6:1ms、7:2ms、8:5ms、9: |
| | 10ms、10:20ms |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<TRG minimum input time>

Type:02h, Category:00h, Item:06h

Target1~4:00h

| Byte | Setting Data |
|------|---|
| 0 | Constant when TRG input terminal: 0:7µs, 1:10µs, 2: |
| U | 20μs, 3:50μs, 4:100μs, 5:200μs, 6:500μs, 7:1ms |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<ENCODER minimum input time>

Type:02h, Category:00h, Item:07h

Target1~4:00h

| byte | Setting Data |
|------|---|
| | Constant when ENCODER input terminal: 0:120ns, 1: |
| 0 | 150ns、2:250ns、3:500ns、4:1µs、5:2µs、6:5µs、7: |
| | 10μs、8:20μs |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Control terminal minimum input time>

Type:02h, Category:00h, Item:08h

| - | |
|------|---|
| byte | Setting Data |
| 0 | Control terminal minimum input time: 0:250µs, 1:1ms |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Change program>

Type:02h, Category:00h, Item:09h

Target1~4:00h

| byte | Setting Data |
|------|---------------------------------------|
| 0 | Change program: 0:Terminal, 1:Command |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

9.2.3Change Program setting

•9.2.3.1Trigger settings

<Trigger mode>

 $Type: 10h \textcolor{red}{\sim} 1Fh (10h: Program \ NO.0, 11h: Program \ NO.1, \cdots,$

1F: Program NO.15)

Category:00h, Item:01h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Trigger mode: 0:Continuous trigger, 1:External |
| U | trigger, 2: Encoder trigger |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Sampling frequency>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F: Program NO.15)

Category:00h, Item:02h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Sampling frequency: 0:10Hz, 1:20Hz, 2:50Hz, 3: 100Hz, 4:200Hz, 5:500Hz, 6:1KHz, 7:2KHz, 8: 4KHz, 9:4.13KHz, 10:8KHz, 11:16KHz, 12:32KHz, 13:64KHz |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Batch measurement>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:00h, Item:03h

Target1~4:00h

| U | |
|------|---|
| byte | Setting Data |
| 0 | Batch measurement: 0:Batch OFF、1:Batch ON |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Inter-trigger pitch>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:00h, Item:04h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Inter-trigger pitch: 0: Pitch OFF、1: Pitch ON |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Inter-trigger pitch count>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:00h, Item:05h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Pitch count: 1~50000(0.001mm unit, 0.001~ |
| 1 | 50.000mm) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Mutual interference prevention>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:00h、Item:06h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Mutual interference prevention: 0:OFF, 1:ON |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Input mode>

 $Type: 10h \sim 1Fh (10h: Program NO.0, 11h: Program NO.1, \cdots,$

1F:Program NO.15)

Category:00h, Item:07h

| byte | Setting Data |
|------|--|
| | Encoder trigger input mode: 0: 1-phase 1TM(no dir_), |
| 0 | 1:2-phase 1times, 2:2-phase 2times, 3:2-phase 4 |
| | times 倍 |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Skipping>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:00h, Item:08h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Encoder trigger skipping: 0: Skipping OFF、1: Skipping ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Points to skip>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F: Program NO.15)

Category:00h, Item:09h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Encoder trigger ekinning count: 2 - 1000 |
| 1 | Encoder trigger skipping count: 2~1000 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Batch count>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:00h, Item:0Ah

Target1~4:00h

| • | |
|------|------------------------|
| byte | Setting Data |
| 0 | Batch count: 50∼15000 |
| 1 | Batch count. 50~ 15000 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

•9.2.3.2 Imaging settings

<Binning>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F: Program NO.15)

Category:01h, Item:01h

 $Target1:00h(headA/wide), 01h(headB), Target2{\sim}4:00h$

| • | , , , , |
|------|-----------------------|
| byte | Setting Data |
| 0 | Binning: 0: OFF、1: ON |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<X direction>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:01h, Item:02h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | Measurement range X direction: 0: FULL, 1: MIDDLE, 2: |
| 0 | SMALL |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Z direction>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:01h, Item:03h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | Measurement range Z direction: 0:FULL, 1:MIDDLE, 2: |
| U | SMALL |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<CMOS sensitivity>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、

1F:Program NO.15)

Category:01h, Item:05h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--|
| | CMOS sensitivity characteristics: 0:High precision, 1:High |
| 0 | dynamic range1、2: High dynamic range2、3: High dynamic |
| | range3 |
| 1 | Reserved (fixed as 0) |
| 2 | Reserved (fixed as 0) |
| 3 | Reserved (fixed as 0) |

<Exposure time>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:01h, Item:06h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Exposure time: 0:15μs, 1:30μs, 2:60μs, 3:120μs, 4:240μs, |
| " | 5:480μs、6:960μs、7:1920μs、8:5ms、9:10ms |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Imaging mode>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:01h, Item:07h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Imaging mode: 0:standard, 1:multi emission(synthesis), 2:multi emission(optimized light intensity) |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Multi emission(optimized light intensity) detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:01h, Item:08h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--------------------------------------|
| 0 | Emission times: 0:2 times, 1:4 times |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Multi emission(synthesis) detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:01h, Item:09h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--------------------------------------|
| 0 | Emission times: 0:3 times, 1:5 times |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Mask setting>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:01h, Item:0Ah

Target1:00h(headA/wide),01h(headB)

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Enabled/disabled: 0: Mask disabled, 1: Rectangle, 2: |
| 0 | Triangle |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | X coordinate1: 2∼640 |
| 5 | A coordinate r. 2∼640 |
| 6 | 7 coordinated 2 - 400 |
| 7 | Z coordinate1: 2∼480 |
| 8 | X coordinate2: 2~640 |
| 9 | A coordinatez. 2~640 |
| 10 | 7 |
| 11 | Z coordinate2: 2~480 |
| 12 | V coordinate 2: 2 - G40 (invalid when Destartin) |
| 13 | X coordinate3: 2~640 (invalid when Rectangle) |
| 14 | Z coordinate3: 2~480 (invalid when Rectangle) |
| 15 | |

<Control mode>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、1F:Program NO.15)

Category:01h, Item:0Bh

 $Target1:00h(headA/wide),\,01h(headB),\,Target2\!\sim\!4:00h$

| byte | Setting Data |
|------|----------------------------------|
| 0 | Control mode: 0: AUTO, 1: MANUAL |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Upper limit value/Lower limit value>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

 $\label{lem:operator} Category: 01h, Item: 0Ch (upper limit value) \ , 0Dh (lower limit value)$

 $Target1:00h(headA/wide), 01h(headB), Target2{\sim}4:00h$

| byte | Setting Data |
|------|----------------------------------|
| 0 | FB upper/lower limit value: 1∼99 |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<FB target area>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:01h, Item:0Eh

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|-------------------------------|
| 0 | ED torget area etarti 0 - 620 |
| 1 | FB target area start: 0∼639 |
| 2 | ED toward area and 0 - 620 |
| 3 | FB target area end: 0∼639 |

<Peak detection level>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:01h, Item:0Fh

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|---------------------------|
| 0 | Peak detection level: 1∼5 |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Invalid data interpolation count>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:01h, Item:10h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | Invalid data interpolation count: 0~255 |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Peak selection>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F: Program NO.15)

Category:01h, Item:11h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| raiget i con (noda) (mao) (o in (noda)) (raiget i in con | |
|---|---|
| byte | Setting Data |
| | Peak selection: 0:Standard, 1:NEAR, 2:FAR, 3: |
| 0 | Remove X multi reflection, 4: Remove Y multi |
| | reflection、5: Make invalid data |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Peak width filter>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:01h, Item:12h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--------------------------------|
| 0 | Peak width filter: 0:OFF, 1:ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

●9.2.3.3 Profile

<Combine(wide)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:02h, Item:01h

Target1~4:00h

| byte | Setting Data |
|------|---------------------------|
| 0 | Wide setting: 0:OFF, 1:ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

Note: This setting is not used when one sensor head.

<Compression(X axis)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:02h, Item:02h

Target1~4:00h

| byte | Setting Data |
|------|--------------------------------------|
| 0 | Compression(X-axis): 0:OFF, 1:2, 2:4 |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Compression(time axis)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:02h, Item:03h

| • | |
|------|-------------------------------------|
| byte | Setting Data |
| 0 | Compression(time axis): 0:OFF, 1:ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Time axis compression count>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:02h, Item:04h

Target1~4:00h

| byte | Setting Data |
|------|---------------------------------------|
| 0 | Time avia compression county 2 - 1000 |
| 1 | Time axis compression count: 2~1000 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Dead zone process valid/invalid>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F: Program NO.15)

Category:02h, Item:05h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Dead zone processing enabled/disabled: 0:disabled. |
| U | 1:enabled |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Reverse(X)/Reverse(Z)>

 $\label{thm:program} Type: 10h \hspace{-0.5mm} \sim \hspace{-0.5mm} 1Fh(10h: Program \hspace{-0.5mm} NO.0, \hspace{-0.5mm} 11h: Program \hspace{-0.5mm} NO.1, \hspace{0.5mm} \cdots, \hspace{0.5mm}$

1F: Program NO.15)

Category:02h, Item:06h(ReverseX), 07h(ReverseZ)

 $Target1:00h(headA/wide),\,01h(headB),\quad Target2{\thicksim}4:00h$

| byte | Setting Data |
|------|-----------------------|
| 0 | Reverse: 0: OFF、1: ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

Note: This setting is not used when one sensor head

<Shift(X)/Shift(Z)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:02h, Item:08h(Shift X), 09h(Shift Z)

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| J | , , , , , |
|------|---|
| byte | Setting Data |
| 0 | Chiff amount, any value in management range |
| 1 | Shift amount: any value in measurement range |
| 2 | (0.001µm unit, Sined 32-bit integer example: 1mm=100000, 2mm=200000) |
| 3 | 1111111=100000, 2111111—200000) |

Note: This setting is not used when one sensor head

<Median(X axis)/Median(time axis)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:02h, Item:0Ah(Median(x axis)), 0Ch(Median(time axis))

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| k | oyte | Setting Data |
|---|------|---|
| | 0 | Median count: 0:OFF, 1:3points, 2:5 points, 3:7 points, |
| | | 4:9 points |
| | 1 | Reserved(fixed as 0) |
| | 2 | Reserved(fixed as 0) |
| | 3 | Reserved(fixed as 0) |

<Smoothing>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:02h, Item:0Bh

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | Smoothing: 0:1, 1:2, 2:4, 3:8, 4:16, 5:32, 6:64 |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Averaging>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:02h, Item:0Dh

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| | byte | Setting Data |
|--|------|---|
| | • | Averaging count: 0:1, 1:2, 2:4, 3:8, 4:16, 5:32, 6: |
| | 0 | 64、7:128、8:256 |
| | 1 | Reserved(fixed as 0) |
| | 2 | Reserved(fixed as 0) |
| | 3 | Reserved(fixed as 0) |

<Invalid data processing(time axis)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:02h, Item:0Eh

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--------------------------|
| 0 | Processing timses: 0~255 |
| 1 | Resume times: 0~255 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Tilt correction>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:02h, Item:0Fh

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | ON/OFF: 0: Correction disabled, 1: Correction |
| U | enabled |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Linear calculation area count: 0: Area2 disabled, 1: |
| 4 | Area2 enabled |
| 5 | Reserved(fixed as 0) |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Area start position1: any value in measurement range |
| 9 | (0.01um unit Sined 32-bit integer |
| 10 | example: 5mm=500000) |
| 11 | czampie. Siiiii—300000/ |
| 12 | Area and position 1: any value in massurement range |
| 13 | Area end position1: any value in measurement range (0.01um unit Sined 32-bit integer |
| 14 | example: 5mm=500000) |
| 15 | example: Jilliii—Joodoo) |
| 16 | Area start position?: any value in measurement range |
| 17 | Area start position2: any value in measurement range (0.01um unit Sined 32-bit integer |
| 18 | example: 5mm=500000) |
| 19 | oxampio. omin-ococco |
| 20 | Area end position2: any value in measurement range |
| 21 | (0.01um unit Sined 32-bit integer |
| 22 | example: 5mm=500000) |
| 23 | елапірів. Эпіпі—Э00000/ |
| 24 | Post-correction angle(-45.00∼+45.00deg): −4500∼ |
| 25 | +4500 |
| 26 | Correction angle(-45.00∼+45.00deg) : −4500∼+ |
| 27 | 4500 |

<Height correction>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:02h, Item:10h

Target1:00h(headA/wide), 01h(headB), Target2~4:00h

| | OnlineadA/wide), orn(neadB), rargetz~4:0011 |
|------|--|
| byte | Setting Data |
| 0 | ON/OFF: 0: Correction disabled, 1: Correction enabled |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Area start position1: any value in measurement range |
| 5 | (0.01um unit Sined 32-bit integer |
| 6 | example: 5mm=500000) |
| 7 | example: Shift—3000007 |
| 8 | Anna and marking a construction in management |
| 9 | Area end position1: any value in measurement range |
| 10 | (0.01um unit Sined 32-bit integer |
| 11 | example: 5mm=500000) |
| 12 | A |
| 13 | Area start position2: any value in measurement range |
| 14 | (0.01um unit Sined 32-bit integer |
| 15 | example: 5mm=500000) |
| 16 | |
| 17 | Area end position2: any value in measurement range |
| 18 | (0.01um unit Sined 32-bit integer |
| 19 | example: 5mm=500000) |
| 20 | |
| 21 | |
| 22 | Post-correction height 0∼999.99mm: 0∼99999 |
| 23 | |
| 24 | Correction span: 1~131071 |
| 25 | *The correction span is the value devided by 65536. |
| 26 | (Condition:0 <correction span<2)<="" td=""></correction> |
| 27 | example: if 98304 is set, (98304÷65536=1.5) |
| | correction span is 1.5. |

●9.2.3.4 Master regist

<Master profile>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:03h, Item:01h

 $Target1:00h(headA/wide),\,01h(headB),\quad Target2{\thicksim}4:$

00h

| byte | Setting Data |
|------|--|
| 0 | valid ∕invalid: 0: Master invalid, 1: Master valid |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Profile data amount (*1): |
| 5 | 50,75,100,150,200,300,400,600,800,1200,1600 |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | |
| 9 | Xcoordinate data start position (*2) |
| 10 | (0.01um unit Sined 32-bit integer) |
| 11 | |
| 12 | |
| 13 | X direction pitch (*2) |
| 14 | (0.01um unit, Sined 32-bit integer) |
| 15 | |
| 16 | |
| 17 | Profile |
| 18 | (0.01um unit Sined 32-bit integer) |
| 19 | |
| ~ | |
| ~ | ~ |
| ~ | |
| ~ | |
| 3212 | |
| 3213 | Profile |
| 3214 | (0.01um unit Sined 32-bit integer) |
| 3215 | |

^{*1} Profile data amount depend on the setting. Refer to 10.2 "Profile data amount calculation method" or receive "MasterProfile" and confirm it.

•9.2.3.5 Position correction settings

<Dual head mode>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、1F:Program NO.15)

Category:04h, Item:01h

Target1~4:00h

| byte | Setting Data |
|------|----------------------|
| | Dual head mode: |
| 0 | 0:OFF、1:ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

Note: This setting is not used when one sensor head.

<Dual head mode target head>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:04h, Item:02h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Correction target head: 0:headA、1:headB |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

Note: This setting is not used when one sensor head.

<Dual head mode X/Z correction amount>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:04h, Item:03h(X correction amount), 04h(Z correctionamount)

Target1~4:00h

*3

| byte | Setting Data |
|------|--|
| 0 | Compatible amount 40000 0 140000 0 |
| 1 | Correction amount: -10000.0~+10000.0mm |
| 2 | (0.001µm unit, Sined 32-bit integer example: |
| 3 | 1mm=100000、2mm=200000) |

Note: This setting is not used when one sensor head $\!\!\!\!_{\circ}$

^{*2} It depends on the type of sensor head and settings. Please confirm by receiving "MasterProfile"

^{*3} This example is in case of 800points(It depends on Profile data amount.)

<θcorrection ON/OFF>< Backup correction ON/OFF>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:04h, Item:05h(θ correctionON/OFF), 07h

(preliminary correctionON/OFF)

Target1:00h(headA/wide),01h(headB)

Target2:00h(Position correction1), 01h(Position

correction2), Target3~4:00h

| byte | Setting Data |
|------|-----------------------|
| 0 | ON/OFF: 0: OFF, 1: ON |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<θcorrection detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:04h, Item:06h (θcorrectionON/OFF)

Target1:00h(headA/wide),01h(headB)

Target2:00h(position correction1), 01h(position

correction2), Target3~4:00h

| byte | Setting Data |
|------|---|
| 0 | Linear calculation area: 0: Area 2 disabled, 1: Area2 |
| U | enabled |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Linear calculation area1 Left: any value in |
| 5 | measurement range |
| 6 | (0.01µm unit Sined 32-bit integer |
| 7 | example: 5mm=500000) |
| 8 | Linear calculation area1 Right: any value in |
| 9 | measurement range |
| 10 | (0.01µm unit Sined 32-bit integer |
| 11 | example: 5mm=500000) |
| 12 | Linear calculation area2 Left: any value in |
| 13 | measurement range |
| 14 | (0.01µm unit Sined 32-bit integer |
| 15 | example: 5mm=500000) |
| 16 | Linear calculation area2 Right: any value in |
| 17 | measurement range |
| 18 | (0.01µm unit Sined 32-bit integer |
| 19 | example: 5mm=500000) |
| 20 | Correction standard: 0: Horizontal,1: MasterProfile |
| 21 | Reserved(fixed as 0) |
| 22 | Reserved(fixed as 0) |
| 23 | Reserved(fixed as 0) |

Xcorrection detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:04h, Item:08h(preliminary correctiondetail), 0Bh

(Xcorrectiondetail)

Target1:00h(headA/wide), 01h(headB)

Target2:00h(position correction1), 01h(position

correction2), Target3~4:00h

| byte | Setting Data |
|------|--|
| 0 | Edge measuring area Left: any value in measurement |
| 1 | range |
| 2 | (0.01um unit Sined 32-bit integer |
| 3 | example: 5mm=500000) |
| 4 | Edge measuring area Right: any value in |
| 5 | measurement range |
| 6 | (0.01um unit Sined 32-bit integer |
| 7 | example: 5mm=500000) |
| 8 | Edge direction: 0:Rising, 1:Falling |
| 9 | Detaction direction: 0: +direction, 1: -direction |
| 10 | Detection No: 1~10 |
| 11 | Reserved(fixed as 0) |
| 12 | Edge level: any value in measurement rease |
| 13 | Edge level: any value in measurement range |
| 14 | (0.01µm unit Sined 32-bit integer |
| 15 | example: 5mm=500000) |

<XZcorrection selection>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F:Program NO.15)

Category:04h, Item:09h

Target1:00h(headA/wide), 01h(headB)

Target2:00h(position correction1), 01h(position correction2),

| byte | Setting Data |
|------|---|
| | XYcorrection selection: 0:OFF, 1:Xcorrection, 2: |
| 0 | Zcorrection, $3:X \rightarrow Z$ correction, $4:Z \rightarrow X$ correction, $5:$ |
| | Feature point correction |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Z correction Height measurement detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:04h, Item:0Ch

Target1:00h(headA/wide),01h(headB)

Target2:00h(position correction1), 01h(position

correction2), Target3~4:00h

| byte | Setting Data |
|------|---|
| 0 | Height measuring area Left: any value in |
| 1 | measurement range |
| 2 | (0.01µm unit Sined 32-bit integer |
| 3 | example: 5mm=500000) |
| 4 | Height measuring area Right: any value in |
| 5 | measurement range |
| 6 | (0.01µm unit Sined 32-bit integer |
| 7 | example: 5mm=500000) |
| 8 | Height type: 0:Peak, 1:bottom, 6:Average |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |

<Featurepoint correction detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:04h, Item:0Dh

Target1:00h(headA/wide), 01h(headB)

Target2:00h(position correction1), 01h(position

correction2), Target3~4:00h

| byte | Setting Data |
|------|---|
| 0 | Correction target selection: 0:Peak, 1:Bottom, 2: |
| | Knee, 3: Intsect(lines), 、4: Contact(lin-arc) |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

*From 4byte, unique parameters are assigned to each correction target. For details on the unique parameters, see 9.2.3.11"Measurement Area" (page-41).

•9.2.3.6Profilemask settings

<Profile mask area settings group>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:05h, Item:01h

Target1:00h(headA/wide),01h(headB), Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Area selection: 0:Disabled, 1:Rectangle, 2:Triangle |
| 1 | position correction selection: 0: No position correction, 1: Position correction1, 2: Position |
| | correction2 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Xcoordinate1: any value in measurement range |
| 5 | (0.01um unit Sined 32-bit integer |
| 6 | example: 5mm=500000) |
| 7 | |
| 8 | Zcoordinate1: any value in measurement range |
| 9 | (0.01um unit Sined 32-bit integer |
| 10 | example: 5mm=500000) |
| 11 | схатріс. Зіпт—300000/ |
| 12 | Vecerdinate 2: any value in massurement range |
| 13 | Xcoordinate2: any value in measurement range |
| 14 | (0.01um unit Sined 32-bit integer |
| 15 | example: 5mm=500000) |
| 16 | ZanadinataO. |
| 17 | Zcoordinate2: any value in measurement range |
| 18 | (0.01um unit Sined 32-bit integer |
| 19 | example: 5mm=500000) |
| 20 | Variable 120 |
| 21 | Xcoordinate3: any value in measurement range |
| 22 | (0.01um unit Sined 32-bit integer |
| 23 | example: 5mm=500000) |
| 24 | 7 |
| 25 | Zcoordinate3: any value in measurement range |
| 26 | (0.01um unit Sined 32-bit integer |
| 27 | example: 5mm=500000) |
| ~ | |
| 139 | |
| | |

*When Rectangle is selected, upper left(Xcoordinate1, Zcoordinate1) and bottom right(Xcoordinate2, Zcoordinate2) should be set. Xcoordinate3, Zcoordinate3 is no effect.

*When Triangle is selected, (Xcoordinate1, Zcoordinate1), (Xcoordinate2, Zcoordinate2) and (Xcoordinate3,

Zcoordinate3) are used.

*1 the number of profile mask area(x5) is continuing.(Total140byte is used.)

- *

<Profile Mask area settings individual>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:05h, Item:02h

Target1:00h(headA/wide),01h(headB)

Target2:00h~04h(Profile mask area1~5) Target3~4:00h

| byte | Setting Data |
|------|---|
| 0 | Area selection: 0:Disabled, 1:Rectangle, 2:Triangle |
| 4 | position correction selection: 0: No position correction, 1: |
| 1 | Position correction1, 2:Position correction2 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Vacardinate1: any value in measurement range |
| 5 | Xcoordinate1: any value in measurement range (0.01um unit Sined 32-bit integer |
| 6 | example: 5mm=500000) |
| 7 | example. Smitt—300000/ |
| 8 | Zcoordinate1: any value in measurement range |
| 9 | (0.01um unit Sined 32-bit integer |
| 10 | example: 5mm=500000) |
| 11 | ехапіріє. Эпіп—300000/ |
| 12 | Vocardinate2: any value in measurement range |
| 13 | Xcoordinate2: any value in measurement range (0.01um unit Sined 32-bit integer |
| 14 | example: 5mm=500000) |
| 15 | example. Jillii – Joodoo / |
| 16 | Zcoordinate2: any value in measurement range |
| 17 | (0.01um unit Sined 32-bit integer |
| 18 | example: 5mm=500000) |
| 19 | example. Jillin—300000/ |
| 20 | Vegerdingtest any value in measurement range |
| 21 | Xcoordinate3: any value in measurement range |
| 22 | (0.01um unit Sined 32-bit integer |
| 23 | example: 5mm=500000) |
| 24 | 7linate2; any value in macaurement range |
| 25 | Zcoordinate3: any value in measurement range |
| 26 | (0.01um unit Sined 32-bit integer |
| 27 | example: 5mm=500000) |

*When Rectangle is selected, upper left(Xcoordinate1, Zcoordinate1) and bottom right(Xcoordinate2, Zcoordinate2) should be set. Xcoordinate3, Zcoordinate3 is no effect.

*When Triangle is selected, (Xcoordinate1, Zcoordinate1), (Xcoordinate2, Zcoordinate2) and (Xcoordinate3, Zcoordinate3) are used.

•9.2.3.7 OUT settings

<OUT name>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F: Program NO.15)

Category:06h, Item:01h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| Byte | Setting Data |
|------|------------------|
| 0 | OUT name,byte1 |
| 1 | OUTname, byte2 |
| 2 | OUT name, byte3 |
| ~ | ~ |
| 19 | OUT name, byte20 |

^{*20} Characters max. 0 is not appended to the end.

<Minimum display unit>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:06h, Item:02h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|----------------------|
| 0 | Minimum display unit |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

^{*}The unit changes according to the measurement mode assigned to the OUT.

Length system, 0:1mm, 1:0.1mm, 2:0.01mm, 3:0.001mm, $4:1\mu m$, $5:0.1\mu m$

Area system, 0:1mm2,1:0.1mm2,2:0.01mm2,3:

 $0.001 mm2, 4\!:\!0.0001 mm2, 5\!:\!0.00001 mm2$

Angle system, 0:1deg, 1:0.1deg, 2:0.01deg

<Measurement mode>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h, Item:03h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | Minimum display unit (from①) |
| 1 | Measurement mode (from②) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | From 4byte, unique parameters are assigned to |
| ~ | each measurement mode. For details on the |
| N | unique parameters, see [Unique parameters of |
| | measurement mode from 4byte] |

1 Length system ... 0:1mm, 1:0.1mm, 2:0.01mm, 3: 0.001mm, 4:1μm, 5:0.1μm

Area system ... 0:1mm², 1:0.1mm², 2:0.01mm², 3: 0.001mm², 4:0.0001mm², 5:0.00001mm²

Angle system ... 0:1deg, 1:0.1deg, 2:0.01deg

2 0:OFF, 1:Height, 2:Step, 3:Position, 4:Center position, 5:Width, 6:Thickness, 7:Angle, 8:R measurement, 9:
Area, 10:Master comparison(Z), 11:Distance(point-point), 12:Distance(point-line), 13:Heigh(Profile compression (time axis) on), 14:Position(Profile compression(time axis) on), 15:Deflection width(Profile compression(time axis) on), 16:Height(simple 3D), 17:Step(simple 3D), 18:Position(simple 3D), 19:Calculation

[Unique parameters of measurement mode from 4byte]

Measurement mode 0:OFF

| byte | Setting Data | |
|------|----------------------|--|
| 4 | | |
| ~ | Reserved(fixed as 0) | |
| 91 | | |

1: Height (when profile compression(time axis) is off)

| byte | Setting Data |
|------|---|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| | Combined profile(only when profile combine(wide) is on) |
| | Measurement target selection: 0: Peak, 1: Bottom, 2: Knee, |
| 5 | 3: Intsect(lines), 4: Intsect(lin-arc), 5: Center of circle, 6: |
| | Average |
| 6 | Position correction selection: 0: No position correction, 1: |
| 0 | Position correction1, 2: Position correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| N | "Measurement Area"(page-41). |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

2:Step

| 2:50 | ер |
|------|---|
| byte | Setting Data |
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| | Combined profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection: 0: Peak, 1: Bottom, 2: Knee, |
| | 3: Intsect(lines), 4: Intsect(lin-arc), 5: Center of circle, 6: |
| | Average |
| 6 | Position correction selection: 0: No position correction, 1: |
| 0 | Position correction1, 2: Position correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| М | "Measurement Area"(page-41). |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 47 | |
| 40 | Reference target head: 0: HeadA, 1: HeadB, 2: Combined |
| 48 | profile(only when profile combine(wide) is on) |
| | Referene target selection: 0:Peak, 1:Bottom, 2: |
| 49 | Knee, 3: Intsect(lines), .4: Contact(lin-arc), 5: |
| | Center of circle, 6: Average |
| | Position correction selection: 0: No position correction, 1: |
| 50 | Position correction1, 2: Position correction2 |
| 51 | Reserved(fixed as 0) |
| 52 | Unique parameters are assigned to each Reference |
| ~ | target. For details on the unique parameters, see |
| N | 9.2.3.11 "Measurement Area" (page-41) |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |
| | |

3: Position (when profile compression(time axis) is off)

| byte | Setting Data |
|------|--|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| 4 | Combined profile(only when profile combine(wide) is on) |
| | Measurement target selection: 0:Peak, 1:Bottom, 2: |
| 5 | Knee, 3:Intsect(lines), 、4:Contact(lin-arc), 5: Center of |
| | circle、7:Edge |
| 6 | Position correction selection: 0: No position correction, 1: |
| O | Position correction1, 2: Position correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| N | "Measurement Area"(page-41). |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

4: Center position, 5: Width

| | , , , , , , , , , , , , , , , , , , , |
|------|---|
| byte | Setting Data |
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| | Combined profile(only when profile combine(wide) is on) |
| | Measurement target selection: 0:Peak, 1:Bottom, 2: |
| 5 | Knee, 3: Intsect(lines), 、4: Contact(lin-arc), 5: Center of |
| | circle、7:Edge |
| 6 | Position correction selection: 0: No position correction, 1: |
| 0 | Position correction1, 2: Position correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see |
| М | 9.2.3.11 "Measurement Area"(page-41). |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 47 | |
| 40 | Reference target selection: 0: HeadA, 1: HeadB, 2: |
| 48 | Combined profile(only when profile combine(wide) is on) |
| | Reference target selection: 0:Peak, 1:Bottom, 2:Knee, |
| 49 | 3: Intsect(lines), 、4: Contact(lin-arc), 5: Center of circle、 |
| | 7:Edge |
| 50 | Position correction selection: 0: No position correction, 1: |
| 30 | Position correction1, 2: Position correction2 |
| 51 | Reserved(fixed as 0) |
| 52 | Unique parameters are assigned to each Reference |
| ~ | target. For details on the unique parameters, see |
| N | 9.2.3.11 "Measurement Area"(page-41). |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

6:Thickness

| | Cotting Date |
|------|---|
| byte | Setting Data |
| 4 | Measurement target selection: 8: Max thickness, 9: |
| | Min thickness, 10: Ave thickness, 11: Max thickness |
| | position, 12: Min thickness position |
| | Position correction selection (HeadA): 0: No |
| 5 | position correction, 1: Position correction1, 2: |
| | Position correction2 |
| | Position correction selection (HeadB): 0: No |
| 6 | position correction, 1: Position correction1, 2: |
| | Position correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each |
| ~ | measurement target. For details on the unique |
| NI | parameters, see 9.2.3.11 "Measurement |
| N | Area"(page-41).。 |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

7:Angle

| /:Ar | Setting Data |
|------|--|
| Dyte | - |
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| | Combined profile(only when profile combine(wide) is on) |
| 5 | Measurement reference selection: |
| | 0:Angle from X-axis, 1:Angle between lines |
| 6 | Angle range: 0:0~180deg, 1:-90~90deg |
| 7 | Measurement target position correction: 0: No position |
| | correction, 1: Position correction1, 2: Position correction2 |
| 8 | Reference target position correction: 0: No position |
| | correction, 1: Position correction1, 2: Position correction2 |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |
| 12 | Measurement target Linear calculation area: 0: |
| 12 | Area2 disabled, 1: Area2enabled |
| 13 | Reserved(fixed as 0) |
| 14 | Reserved(fixed as 0) |
| 15 | Reserved(fixed as 0) |
| 16 | Measurement target Linear calculation area Left: |
| 17 | any value in measurement range |
| 18 | (0.01µm unit Sined 32-bit integer |
| 19 | example: 5mm=500000) |
| 20 | Measurement target Linear calculation area Right: |
| 21 | any value in measurement range |
| 22 | (0.01µm unit Sined 32-bit integer |
| 23 | example: 5mm=500000) |
| 24 | Measurement target Linear calculation area2 Left: |
| 25 | any value in measurement range |
| 26 | (0.01µm unit Sined 32-bit integer |
| 27 | example: 5mm=500000) |
| 28 | Measurement target Linear calculation area2 Right: |
| 29 | any value in measurement range |
| 30 | (0.01µm unit Sined 32-bit integer |
| 31 | example: 5mm=500000) |
| | Reference target Linear calculation area: 0:Area2 |
| 32 | disabled, 1: Area2 enabled |
| 33 | Reserved(fixed as 0) |
| 34 | Reserved(fixed as 0) |
| 35 | Reserved(fixed as 0) |
| 36 | Reference target Linear calculation area Left: |
| 37 | any value in measurement range |
| 38 | (0.01µm unit Sined 32-bit integer |
| 39 | example: 5mm=500000) |
| | • |

| 40 | Reference target Linear calculation area Right: |
|----|--|
| 41 | any value in measurement range |
| 42 | (0.01µm unit Sined 32-bit integer |
| 43 | example: 5mm=500000) |
| 44 | Reference target Linear calculation area2 Left: |
| 45 | any value in measurement range |
| 46 | (0.01µm unit Sined 32-bit integer |
| 47 | example: 5mm=500000) |
| 48 | Reference target Linear calculation area2 Right: |
| 49 | any value in measurement range |
| 50 | (0.01µm unit Sined 32-bit integer |
| 51 | example: 5mm=500000) |
| 52 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

8:R measurement

| byte | Setting Data |
|------|---|
| | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| 4 | Combined profile(only when profile combine(wide) |
| | is on) |
| | Position correction selection: 0: No position |
| 5 | correction, 1: Position correction1, 2: Position |
| | correction2 |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| | Arc calculation area: 0: Area2 disabled, 1: Area2 |
| 8 | enabled |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |
| 12 | Arc calculation area Left: any value in |
| 13 | measurement range |
| 14 | (0.01µm unit Sined 32-bit integer |
| 15 | example: 5mm=500000) |
| 16 | Arc calculation area Right: any value in |
| 17 | measurement range |
| 18 | (0.01µm unit Sined 32-bit integer |
| 19 | example: 5mm=500000) |
| 20 | Arc calculation area2 Left: any value in |
| 21 | measurement range |
| 22 | (0.01µm unit Sined 32-bit integer |
| 23 | example: 5mm=500000) |
| 24 | Arc calculation area2 Right: any value in |
| 25 | measurement range |
| 26 | (0.01µm unit Sined 32-bit integer |
| 27 | example: 5mm=500000) |
| 28 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

9:Area

| 9:A | iea |
|------|--|
| byte | Setting Data |
| 5 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined |
| | profile(only when profile combine(wide) is on) |
| | Measurement reference selection: 0:Reference for 1 line, 1: |
| | Reference for 2 lines, 2: Master reference |
| 6 | Measurement target position correction: 0: No position |
| | correction, 1: Position correction1, 2: Position correction2 |
| 7 | Measurement target1 position correction: 0: No position |
| | correction, 1: Position correction1, 2: Position correction2 |
| 8 | Measurement target2 position correction: 0: No position |
| | correction, 1: Position correction1, 2: Position correction2 |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |
| 12 | Measurement area Area calculation area Left: any |
| 13 | value in measurement range (0.01µm unit Sined |
| 14 | 32-bit integer |
| 15 | example: 5mm=500000) |
| 16 | Measurement area Area calculation area Right: any |
| 17 | value in measurement range (0.01µm unit Sined |
| 18 | 32-bit integer |
| 19 | example: 5mm=500000) |
| 20 | Linear calculation area: 0: Area2 disabled, 1: Area2 enabled |
| 21 | Reserved(fixed as 0) |
| 22 | Reserved(fixed as 0) |
| 23 | Reserved(fixed as 0) |
| 24 | Reference straight line1 Linear calculation area Left: |
| 25 | any value in measurement range (0.01µm unit Sined |
| 26 | 32-bit integer |
| 27 | example: 5mm=500000) |
| 28 | Reference straight line1 Linear calculation area |
| 29 | Right: any value in measurement range (0.01µm unit |
| 30 | Sined 32-bit integer |
| 31 | example: 5mm=500000) |
| 32 | Reference straight line1 Area2 Left: any value in |
| 33 | measurement range |
| 34 | (0.01µm unit Sined 32-bit integer |
| 35 | example: 5mm=500000) |
| 36 | Reference straight line1 Area2 Right: any value in |
| 37 | measurement range |
| 38 | (0.01µm unit Sined 32-bit integer |
| 39 | example: 5mm=500000) |
| 40 | Linear calculation area: 0: Area2 disabled, 1: Area2 enabled |
| 41 | Reserved(fixed as 0) |
| 42 | Reserved(fixed as 0) |

| 43 | Reserved(fixed as 0) |
|----|--|
| 44 | Reference straight line2 Linear calculation area Left: |
| 45 | any value in measurement range (0.01µm unit Sined |
| 46 | 32-bit integer |
| 47 | example: 5mm=500000) |
| 48 | Reference straight line2 Linear calculation area |
| 49 | Right: any value in measurement range (0.01µm unit |
| 50 | Sined 32-bit integer |
| 51 | example: 5mm=500000) |
| 52 | Reference straight line2 area2 Left: any value in |
| 53 | measurement range |
| 54 | (0.01µm unit Sined 32-bit integer |
| 55 | example: 5mm=500000) |
| 56 | Reference straight line2 area2 Right: any value in |
| 57 | measurement range |
| 58 | (0.01µm unit Sined 32-bit integer |
| 59 | example: 5mm=500000) |
| 60 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

^{*}Reference straight line2's settings are not needed when Reference for 1 line is selected.

10: Master comparison(Z)

| byte | Setting Data |
|------|--|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| | Combined profile(only when profile combine(wide) is on) |
| 5 | Position correction selection: 0: No position correction, 1: |
| 3 | Position correction1, 2: Position correction2 |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Anna antica I office and a large in the second and a second a second and a second a |
| 9 | Area setting Left: any value in measurement range |
| 10 | (0.01µm unit Sined 32-bit integer |
| 11 | example: 5mm=500000) |
| 12 | Annual Mine Diebt. |
| 13 | Area setting Right: any value in measurement range |
| 14 | (0.01µm unit Sined 32-bit integer |
| 15 | example: 5mm=500000) |
| 16 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

11: Distance(point-point)

| byte | Setting Data |
|------------|--|
| Dyto | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| 4 | |
| | Combined profile(only when profile combine(wide) |
| | is on) |
| _ | Measurement target selection: 0: Peak, 1: Bottom, |
| 5 | 2: Knee, 3: Intsect(lines), .4: Contact(lin-arc), 5: |
| | Center of circle |
| | Position correction selection: 0: No position |
| 6 | correction, 1: Position correction1, 2: Position |
| | correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each |
| ~ | measurement target. For details on the unique |
| М | parameters, see 9.2.3.11 "Measurement |
| | Area"(page-41).。 |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 47 | |
| | Reference target selection: 0: HeadA, 1: HeadB, 2: |
| 48 | Combined profile(only when profile combine(wide) |
| | is on) |
| | Reference target selection: 0:Peak, 1:Bottom, 2: |
| 49 | Knee, 3: Intsect(lines), .4: Contact(lin-arc), 5: |
| | Center of circle |
| | Position correction selection: 0: No position |
| 50 | correction, 1: Position correction1, 2: Position |
| | correction2 |
| 51 | Reserved(fixed as 0) |
| 52 | Unique parameters are assigned to each Reference |
| ~ | target. For details on the unique parameters, see |
| N | 9.2.3.11 "Measurement Area"(page-41).。 |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |
| <u>`</u> . | |

^{*}Reference straight line1, 2's settings are not needed whenMaster Reference is selected.

12: Distance(point-line)

| byte | Setting Data |
|------|--|
| byte | · · |
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined |
| | profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection: 0:Peak, 1:Bottom, 2:Knee, 3: |
| | Intsect(lines), 、4: Contact(lin-arc), 5: Center of circle |
| 6 | Position correction selection: 0: No position correction, 1: |
| | Position correction1, 2: Position correction2 |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| М | "Measurement Area"(page-41). |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 47 | |
| 40 | Reference target selection: 0: HeadA, 1: HeadB, 2: Combined |
| 48 | profile(only when profile combine(wide) is on) |
| 49 | Position correction selection: 0: No position correction, 1: |
| 49 | Position correction1, 2: Position correction2 |
| 50 | Reserved(fixed as 0) |
| 51 | Reserved(fixed as 0) |
| 52 | Linear calculation area: 0: Area2 disabled, 1: Area2 enabled |
| 53 | Reserved(fixed as 0) |
| 54 | Reserved(fixed as 0) |
| 55 | Reserved(fixed as 0) |
| 56 | Linear calculation area Left: any value in |
| 57 | measurement range |
| 58 | (0.01µm unit Sined 32-bit integer |
| 59 | example: 5mm=500000) |
| 60 | Linear calculation area Right: any value in |
| 61 | measurement range |
| 62 | (0.01µm unit Sined 32-bit integer |
| 63 | example: 5mm=500000) |
| 64 | |
| 65 | Area2 Left: any value in measurement range |
| 66 | (0.01µm unit Sined 32-bit integer |
| 67 | example: 5mm=500000) |
| 68 | |
| 69 | Area2 Right: any value in measurement range |
| 70 | (0.01µm unit Sined 32-bit integer |
| 71 | example: 5mm=500000) |
| 72 | |
| ~ | Reserved(fixed as 0) |
| 91 | |
| J1 | |

13: Height (when profile compression(time axis) is on)

| byte | Setting Data |
|------|--|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| | Combined profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection: 0:Peak, 1:bottom, 、13: |
| | Middle value |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| N | "Measurement Area"(page-41). |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

14: Position(when profile compression(time axis) is on)

| byte | Setting Data |
|------|--|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined |
| 4 | profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection: 0:Peak, 1:bottom, 7:Edge |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| N | "Measurement Area"(page-41). |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

15: Deflection width(when profile compression(time axis) is on)

| byte | Setting Data |
|------|---|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: |
| 4 | Combined profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection: 14:P-P(Z), 15:P-P(X) |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each |
| ~ | measurement target. For details on the unique |
| N | parameters, see 9.2.3.11 "Measurement |
| IN | Area"(page-41). |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

16: Height (simple 3D)

| byte | Setting Data |
|------|---|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined |
| | profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection:0:Peak,1:bottom,6:Average,16:P-P |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| М | "Measurement Area"(page-41). |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 15 | |
| 16 | Ycoordinate start position: value withinBatch point |
| 17 | r coordinate start position. Value withinbatch point |
| 18 | Ycoordinate endposition:value withinBatch point |
| 19 | r coordinate enuposition, value within battin point |
| 20 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

17: Step (simple 3D)

| byte | Setting Data |
|------|---|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined |
| | profile(only when profile combine(wide) is on) |
| 5 | Measurement target selection: 0:Peak, 1:bottom, 6:Average |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| М | "Measurement Area"(page-41). |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 15 | |
| 16 | Measurement target Ycoordinate start position: |
| 17 | value withinBatch point |
| 18 | Measurement target Ycoordinate end position: |
| 19 | value withinBatch point |
| 20 | Reference target selection: 0: HeadA, 1: HeadB, 2: Combined |
| 20 | profile(only when profile combine(wide) is on) |
| 21 | Reference target selection: 0:Peak, 1:bottom, 6:Average |
| 22 | Reserved(fixed as 0) |
| 23 | Reserved(fixed as 0) |
| 24 | Unique parameters are assigned to each reference |
| ~ | target. For details on the unique parameters, see |
| М | 9.2.3.11 "Measurement Area"(page-41).。 |

| M+1 | |
|-----|--|
| ~ | Reserved(fixed as 0) |
| 31 | |
| 32 | Reference target Ycoordinate start position: |
| 33 | value withinBatch point |
| 34 | Reference target Ycoordinate end position: |
| 35 | value withinBatch point |
| 36 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

18: Position (simple 3D)

| byte | Setting Data |
|------|--|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined |
| 4 | profile(only when profile combine(wide) is on) |
| 5 | Output coordinate: 0: Xcoordinate, 1: Ycoordinate |
| 6 | Measurement target selection: 0:Peak, 1:bottom |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each measurement |
| ~ | target. For details on the unique parameters, see 9.2.3.11 |
| М | "Measurement Area" (page-41). |
| M+1 | |
| ~ | Reserved(fixed as 0) |
| 15 | |
| 16 | Ycoordinatestart position: value withinBatch point |
| 17 | r coordinatestart position. Value withinbatch point |
| 18 | Ycoordinate end position: value withinBatch point |
| 19 | r coordinate end position. Value withinbattin point |
| 20 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

19: Calculation

| byte | Setting Data |
|------|---|
| 4 | Calculation mode: 0: Addition, 1: Subtraction. 2: |
| | Absolute value, 3:AVE, 4:P-P, 5:MAX, 6:MIN |
| 5 | Reserved(fixed as 0) |
| 6 | Reserved(fixed as 0) |
| 7 | Reserved(fixed as 0) |
| 8 | Unique parameters are assigned to each |
| ~ | calculation mode. The unique parameters are |
| N | described below. |
| N+1 | |
| ~ | Reserved(fixed as 0) |
| 91 | |

[Unique parameter of calculation from 8byte]

0: Addition 1: Subtraction

| byte | Setting Data |
|------|--|
| 8 | Calculation target A: OUT number (example: |
| 0 | OUT1:00h、OUT12:0Bh) |
| 9 | Calculation target B: OUT number (example: |
| 9 | OUT1:00h、OUT12:0Bh) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |

2: Absolute value

| byte | Setting Data |
|------|--|
| 8 | Target OUT: OUT number (example: OUT1:00h, |
| | OUT12:0Bh) |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |

3: AVE/ 4: P-P/ 5: MAX/ 6: MIN

| byte | Setting Data |
|------|---|
| 0 | OUT1: 0: Do not use as calculation target, 1: Use as |
| 8 | calculation target |
| | OUT2~15: 0: Do not use as calculation target, 1: |
| | Use as calculation target |
| 23 | OUT16: 0: Do not use as calculation target, 1: Use as |
| 23 | calculation target |

<Measurement value hold count>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:06h, Item:04h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| • | _ |
|------|---------------------------------------|
| byte | Setting Data |
| 0 | Management value hald accepts 0 - 000 |
| 1 | Measurement value hold count: 0∼999 |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Measurement value filter>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、1F:Program NO.15)

Category:06h, Item:05h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|--|
| | Measurement value filter: 0:OFF, 1:Moving Average, |
| 0 | 2: Low-pass filter, 3: High-pass filter |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Measurement valuefilter detail>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h, Item:06h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

Unique parameters are assigned to each measurement value filter.

1: Moving average

| byte | Setting Data |
|------|---|
| 0 | Averagecount: 0:4 times, 1:16 times, 2:64 times, 3: |
| 0 | 256 times, 4:1024 times, 5:4096 times |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

2:Low-pass filter

3: High-pass filter

| Byte | Setting Data |
|------|---|
| 0 | Cutoff frequency: 0:0.1Hz, 1:0.3Hz, 2:1Hz, 3:3Hz, |
| U | 4:10Hz、5:30Hz、6;100Hz、7:300Hz、8:1000Hz |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

- <Scaling measurement value1>
- <Scaling display value1>
- <Scaling measurement value2>
- <Scaling display value2>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h, Item:07h(Scaling measurement value1), 08h (Scaling display value1), 09h(Scaling measurement value2), 0Ah (Scaling display value2)

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|---|
| 0 | Measurement value/Display value: 0.01µm unit Sined |
| 1 | 32-bit integer. |
| 2 | *Display range lower limit for the minimum display unit |
| 3 | ≦Measurement value/Display value ≦Display range |
| | upper limit for the minimum display unit. |

<Measuring mode>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、1F:Program NO.15)

Category:06h, Item:0Bh

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|--|
| | Measuring mode: 0:Normal, 1:Peak hold, 2:bottom |
| 0 | hold, 3: Peak to Peak hold, 4: Average hold, 5: Sample |
| | hold, 6:Peak、7:bottom、8:Peak to Peak、9:Average |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Measuring period>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h、Item:0Ch

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|--|
| | Measuring period: 0:Terminal/command, 1: |
| 0 | Measurement area 2 : OUT reference, 3: |
| | Threshhold(level), 、4:Threshhold(Edge) |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Unique parameters are assigned to each macauries |
| ~ | Unique parameters are assigned to each measuring |
| 15 | period. The unique parameters are described below. |

[Unique parameters of Measuring period from 4byte]

1: Measurement area

| THE GOLD THE STATE OF THE STATE | |
|--|--|
| byte | Setting Data |
| 4 | Measure start position: value withinBatch point |
| 5 | Measure start position. Value withinbatter point |
| 6 | Manager and position, value within Datab point |
| 7 | Measure end position: value withinBatch point |
| 8 | |
| ~ | Reserved(fixed as 0) |
| 15 | |

2:OUT reference

| byte | Setting Data | |
|------|--|--|
| 4 | Reference OUT: 0:OUT1, 1:OUT2···15:OUT16 | |
| 5 | | |
| ~ | Reserved(fixed as 0) | |
| 15 | | |

3: Threshold (level)

| byte | Setting Data |
|------|---|
| 4 | Upper limit: 0.01µm unit. Sined 32-bit integer。 |
| 5 | *Display range lower limit for the minimum |
| 6 | display unit ≦Upper limit ≦display range |
| 7 | upper limit for the minimum display unit |
| 8 | Lower limit: 0.01µm unit, Sined 32-bit integer, |
| 9 | *Display range lower limit for the minimum |
| 10 | display unit ≦Lower limit ≦dislay range |
| 11 | upper limit for the minimum display unit |
| 12 | |
| ~ | Reserved(fixed as 0) |
| 15 | |

4: Threshold (Edge)

| byte | Setting Data |
|------|--|
| 4 | Edge threshold: 0.01µm unit. Sined 32-bit |
| 5 | integer _° |
| 6 | *Display range lower limit for the minimum |
| 7 | display unit ≦Edge threshold ≦display range |
| 7 | upper limit for the minimum display unit |
| 8 | Edge direction: 0:Rising, 1:Falling |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |
| 12 | Management |
| 13 | Measurement count: |
| 14 | when batch off: Integer from 1 to 999,999 |
| 15 | when batch on: Integer from 1 to Batch point |

<Offset>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h、Item:0Dh

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Offset: 0.01µm unit. Sined 32-bit integer。 |
| 1 | *Display range lower limit for the minimum display unit |
| 2 | \leq Offset \leq display range upper limit for the minimum |
| 3 | display unit |

<Tolerance upper/lower limit>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h, Item:0Eh(upper limit), 0Fh(lower limit)

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data | |
|------|---|--|
| 0 | Tolerance upper/lower limit value: 0.01µm unit. Sined | |
| 1 | 32-bit integer. | |
| 2 | *Display range lower limit for the minimum display unit | |
| 3 | ≦Tolerance upper/lower limit value ≤display range | |
| | upper limit for the minimum display unit | |

<Zero reference value>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h, Item:13h

Target1:00h \sim 0Fh(OUT1 \sim 16) Target2 \sim 4:00h

| byte | Setting Data |
|------|---|
| 0 | Zero reference value: 0.01µm unit. Sined 32-bit |
| 1 | integer. |
| 2 | *Display range lower limit for the minimum display unit |
| 3 | ≦Zero reference value≦display range upper limit for |
| | the minimum display unit |

<Hysteresis>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、

1F:Program NO.15)

Category:06h, Item:10h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Hysteresis: 0.01µm unit. Sined 32-bit integer. *0 ≦Hysteresis ≦display range upper limit for the minimum display unit |
| 1 | |
| 2 | |
| 3 | |

<ZERO>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:06h、Item:11h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data |
|------|--------------------------------|
| 0 | ZERO: 0:None, 1:ZERO1, 2:ZERO2 |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<TIMING/RESET>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:06h, Item:12h

 $Target1:00h \sim 0Fh(OUT1 \sim 16) \quad Target2 \sim 4:00h$

| byte | Setting Data | |
|------|--|--|
| 0 | TIMING/RESET: 0: None, 1: TIMING1/RESET1, 2: | |
| | TIMING2/RESET2 | |
| 1 | Reserved(fixed as 0) | |
| 2 | Reserved(fixed as 0) | |
| 3 | Reserved(fixed as 0) | |

•9.2.3.8 Terminal settings

<Judgment output setting>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:07h, Item:01h

Target1:00h~0Bh(OUT_PIN1~12) Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | Setting method: 0:No setting, 1:AND, 2:OR |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | OUT1 judgment result: 0:Not specified, 2:HI, 4:GO, 8:LO |
| 5 | OUT2 judgment result: 0:Not specified, 2:HI, 4:GO, 8:LO |
| ~ | ~ |
| 21 | OUT16 judgment result: 0:Not specified, 2:HI, 4:GO, 8:LO |

*The judgment result can be specified by bits with logical OR .

When HI and GO are both specified, the measurement result value is "6".

<Analog output target OUT>

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、1F:Program NO.15)

Category:07h, Item:02h

Target1:00h(CH1),01h(CH2) Target2~4:00h

| byte | Setting Data | |
|------|---|--|
| 0 | Target OUT: 0:OUT1, 1:OUT215:OUT16, 255: none | |
| 1 | Reserved(fixed as 0) | |
| 2 | Reserved(fixed as 0) | |
| 3 | Reserved(fixed as 0) | |

<Analog output scaling>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F: Program NO.15)

Category:07h, Item:03h

Target1:00h(CH1),01h(CH2) Target2~4:00h

| byte | Setting Data |
|------|--|
| 0 | <u> </u> |
| 1 | OUT display value1: Sined 32-bit integer |
| 2 | *1 |
| 3 | • |
| 4 | |
| 5 | Output voltage1: Sined 32-bit integer |
| 6 | -10.5V~10.5V(1mVunit) |
| 7 | |
| 8 | |
| 9 | OUT display value2: Sined 32-bit integer |
| 10 | *1 |
| 11 | |
| 12 | |
| 13 | Output voltage2: Sined 32-bit integer |
| 14 | -10.5V~10.5V(1mVunit) |
| 15 | |

^{*1} setting range

Length(mm)...-999.999mm \sim 999.999mm (0.01 μ m unit)

Area(mm^2)...-9999.99mm^2~9999.99mm^2

(0.00001mm^2unit)

Angle(deg)...-9999.99deg~9999.99deg (0.001degunit)

•9.2.3.9 Storage settings

<Storage target>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ...,

1F: Program NO.15)

Category:08h, Item:01h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Storage target: 0:OFF, 1:OUT value, 2:Profile |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Storage condition>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:08h, Item:02h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Storage condition: 0:Terminal/Command、1: OUT |
| | update, 2:OUT data(edge), 3:OUT data(level) |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |

<Storage data amount(Terminal/Command)>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:08h, Item:03h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Oleman data annual Ota bellandia annual linit |
| 1 | Storage data amount: 0 to buffer size upper limit. *Upper limit value is the max points can be set by |
| 2 | LJ-Navigator2. |
| 3 | Lo-ivavigatorz. |

<Storage data amount(OUT data(Edge))>

Type:10h~1Fh(10h:Program NO.0, 11h:Program NO.1, ..., 1F:Program NO.15)

Category:08h, Item:04h

Target1~4:00h

| byte | Setting Data |
|------|--|
| 0 | Storage data amount: 0 to buffer size upper limit. *Upper limit value is the max points can be set by LJ-Navigator2. |
| 1 | |
| 2 | |
| 3 | LO-INAVIGATOIZ. |
| 4 | Threshold: The range that can be input in the OUT |
| 5 | |
| 6 | minimum display unit. (0.01µm unit. Sined 32-bit integer) |
| 7 | integer) |
| 8 | Hyptorogic: 0 < Hyptorogic < dipplay range upper |
| 9 | Hysteresis: 0 ≦Hysteresis ≦ display range upper |
| 10 | limit for the minimum display unit.(0.01µm unit.Sined 32-bit integer) |
| 11 | วะ-มน integer/ |
| 12 | Target OUT: 0:OUT1, 1:OUT2, 2:OUT3···15: |
| 12 | OUT16 |
| 13 | Edgedirection: 0: Rising, 1: Falling |
| 14 | Reserved(fixed as 0) |
| 15 | Reserved(fixed as 0) |

<Storage data amount (OUT data(level) >

Type:10h~1Fh(10h:Program NO.0、11h:Program NO.1、…、1F:Program NO.15)

Category:08h, Item:05h

Target1~4:00h

| byte | Setting Data |
|------|---|
| 0 | Lippor limit value: The range that can be input in the |
| 1 | Upper limit value: The range that can be input in the OUT minimum display unit. (0.01µm unit. Sined 32-bit integer) |
| 2 | |
| 3 | |
| 4 | Lower limit value: The range that can be input in the |
| 5 | Lower limit value: The range that can be input in the OUT minimum display unit. (0.01µm unit. Sined 32-bit integer) |
| 6 | |
| 7 | |
| 8 | Target OUT: 0:OUT1、1:OUT2···15:OUT16 |
| 9 | Reserved(fixed as 0) |
| 10 | Reserved(fixed as 0) |
| 11 | Reserved(fixed as 0) |

●9.2.3.10 Program name

<Program name>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1, ···, 1F:Program NO.15)

Category:09h、Item:00h

Target1~4:00h

| byte | Setting Data |
|------|----------------------|
| 0 | Program name, byte0 |
| 1 | Program name, byte1 |
| 2 | Program name, byte2 |
| ~ | ~ |
| 23 | Program name, byte23 |

^{*24} characters max. 0 is not appended to the end.

•9.2.3.11 Measurement area details

The correction target selection of feature point correction of position correction and the unique parameters of the measurement target of the measurement mode are shown below. The byte numbers shown here indicate the byte numbers from the start of the corresponding data block. (see the example at 9.2.3.12)

0: Peak, 1: bottom, 6: Average, 8: Maximum thickness, 9: Minimum thickness, 10: Average thickness, 11: Maximum thickness position, 12: Minimum thickness position, 13: Middle value, 14: P-P(Z) (only when profile compression(time axis) is on),16: P-P(only for Height (simple 3D)

| byte | Setting Data |
|------|---|
| 0 | |
| 1 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer |
| 2 | example: 5mm=500000) |
| 3 | |
| 4 | Area Right: any value in maccurement range |
| 5 | Area Right: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) |
| 6 | |
| 7 | |

2:Knee

| byte | Setting Data |
|------|---|
| 0 | Area Left: any value in measurement range |
| 1 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) |
| 2 | |
| 3 | |
| 4 | A. Dishta and a in a second and a second a second and a second a second and a second a second and a second and a second a second a second a second a second and a second and a second and a second a second a second |
| 5 | Area Right: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) |
| 6 | |
| 7 | |
| 8 | Knee shape: 0:Valley, 1:Peak |
| 9 | Detection direction: 0: + direction, 1: - direction |
| 10 | Detection No: 1~10 |
| 11 | Sensitivity: 0~100 |

3:Intersection(lines)

| Section(lines) Setting Data |
|---|
| Linear calculation area: 0: Area2 disabled, 1: |
| Area2 enabled |
| Reserved(fixed as 0) |
| Reserved(fixed as 0) |
| Reserved(fixed as 0) |
| |
| Line calculation area Left: Any value in |
| measurement range (0.01µm unit Sined |
| 32-bit integer. example: 5mm=500000) |
| |
| Line calculation area Right: Any value in |
| measurement range (0.01µm unit Sined |
| 32-bit integer. example: 5mm=500000) |
| |
| Area2 Left: Any value in measurement range |
| (0.01µm unit Sined 32-bit integer. example: |
| 5mm=500000) |
| |
| Area2 Right: Any value in measurement |
| range (0.01µm unit Sined 32-bit integer. |
| example: 5mm=500000) |
| Linear calculation area count: 0: Area2 |
| disabled, 1: Area2 enabled |
| Reserved(fixed as 0) |
| Reserved(fixed as 0) |
| Reserved(fixed as 0) |
| Line coloulation area. Left: Assurable is |
| Line calculation area Left: Any value in measurement range (0.01µm unit Sined |
| 32-bit integer. example: 5mm=500000) |
| 52 bit integer. example. Smith—3000007 |
| Line colculation area. Right: Anyundus in |
| Line calculation area Right: Any value in measurement range (0.01µm unit Sined |
| 32-bit integer. example: 5mm=500000) |
| 52-5it integer. example. Sitiff—500000) |
| Aroa 2 Loft: Any value in macaurament re- |
| Area2 Left: Any value in measurement range |
| (0.01µm unit Sined 32-bit integer. example: 5mm=500000) |
| Jillii — 300000/ |
| |
| Arong Dights Answerles in any arrange |
| Area2 Right: Any value in measurement |
| Area2 Right: Any value in measurement range (0.01µm unit Sined 32-bit integer. example: 5mm=500000) |
| |

4: Contact (line-arc)

Line1

Line2

| byte | Setting Data | |
|------|--|------|
| Byte | Linear calculation area: 0: Area2 disabled, 1: | |
| 0 | Area2 enabled | |
| 1 | Reserved(fixed as 0) | |
| 2 | Reserved(fixed as 0) | |
| 3 | Reserved(fixed as 0) | |
| 4 | | |
| 5 | Line calculation area Left: Any value in | |
| 6 | measurement range (0.01µm unit Sined 32-bit | |
| 7 | integer. example: 5mm=500000) | |
| 8 | | |
| 9 | Line calculation area Right: Any value in | Line |
| 10 | measurement range (0.01µm unit Sined 32-bit | |
| 11 | integer. example: 5mm=500000) | |
| 12 | | |
| 13 | Area2 Left: Any value in measurement range | |
| 14 | (0.01µm unit Sined 32-bit integer. example: | |
| 15 | 5mm=500000) | |
| 16 | Access District Access to the control of the contro | |
| 17 | Area2 Right: Any value in measurement range | |
| 18 | (0.01µm unit Sined 32-bit integer. example: 5mm=500000) | ノ |
| 19 | 511111—5000000) | |
| 20 | Arc calculation area: 0: Area2 disabled, 1: Area2 | |
| 20 | enabled | |
| 21 | Reserved(fixed as 0) | |
| 22 | Reserved(fixed as 0) | |
| 23 | Reserved(fixed as 0) | |
| 24 | Arc calculation area Left: Any value in | |
| 25 | measurement range (0.01µm unit Sined 32-bit | |
| 26 | integer. example: 5mm=500000) | |
| 27 | | |
| 28 | Arc calculation area Right: Any value in | Arc |
| 29 | measurement range (0.01µm unit Sined 32-bit | |
| 30 | integer. example: 5mm=500000) | |
| 31 | | |
| 32 | Area2 Left: Any value in measurement range | |
| 33 | (0.01µm unit Sined 32-bit integer. example: | |
| 34 | 5mm=500000) | |
| 35 | | |
| 36 | Area2 Right: Any value in measurement range | |
| 37 | (0.01µm unit Sined 32-bit integer. example: | |
| 38 | 5mm=500000) | ノ |
| 39 | | |

42

5: Centerof circle

| byte | Setting Data |
|------|--|
| 0 | Arc calculation areacount: 0: Area2 disabled, 1: |
| U | Area2 enabled |
| 1 | Reserved(fixed as 0) |
| 2 | Reserved(fixed as 0) |
| 3 | Reserved(fixed as 0) |
| 4 | Ana calculation area I off. |
| 5 | Arc calculation area Left: |
| 6 | any value in measurement range (0.01µm unit |
| 7 | Sined 32-bit integer example: 5mm=500000) |
| 8 | |
| 9 | Arc calculation area Right: |
| 10 | any value in measurement range (0.01µm unit |
| 11 | Sined 32-bit integer example: 5mm=500000) |
| 12 | Anna Carlotta anna anna anna anna anna anna |
| 13 | Area2 Left: any value in measurement range |
| 14 | (0.01µm unit Sined 32-bit integer example: |
| 15 | 5mm=500000) |
| 16 | Area2 Right: any value in measurement |
| 17 | range |
| 18 | (0.01µm unit Sined 32-bit integer example: |
| 19 | 5mm=500000) |

7: Edge (when profile compression(time axis) is off)

| byte | Setting Data |
|------|--|
| 0 | Edge measuring area Left: any value in measurement |
| 1 | range |
| 2 | (0.01µm unit Sined 32-bit integer |
| 3 | example: 5mm=500000) |
| 4 | Edge measuring area Right: any value in |
| 5 | measurement range |
| 6 | (0.01µm unit Sined 32-bit integer |
| 7 | example: 5mm=500000) |
| 8 | Edge direction: 0:Rising, 1:Falling |
| 9 | Detect direction: 0: +direction, 1: -direction |
| 10 | Detect No: 1∼10 |
| 11 | Reserved(fixed as 0) |
| 12 | Edge level. Any value in magazirement range |
| 13 | Edge level: Any value in measurement range |
| 14 | (0.01µm unit Sined 32-bit integer example: 5mm=500000) |
| 15 | example. Jillii—Juuuuu |

7: Edge (when profile compression(time axis) is on)

| byte | Setting Data |
|------|---|
| 0 | Edge measuring area Left: any value in measurement |
| 1 | range |
| 2 | (0.01µm unit Sined 32-bit integer |
| 3 | example: 5mm=500000) |
| 4 | Edge measuring area Right: any value in |
| 5 | measurement range |
| 6 | (0.01µm unit Sined 32-bit integer |
| 7 | example: 5mm=500000) |
| 8 | Detection target: 0: Upper profile, 1: Lower profile |
| 9 | Edge direction: 0:Rising, 1:Falling |
| 10 | Detect direction: 0:+direction, 1:-direction |
| 11 | Detect No: 1∼10 |
| 12 | Edge level; any value in magazirement range |
| 13 | Edge level: any value in measurement range (0.01µm unit Sined 32-bit integer |
| 14 | example: 5mm=500000) |
| 15 | coample. Sillii—300000/ |

15:P-P(X) (only for when profile compression (time axis) is on)

| byte | Setting Data |
|------|---|
| 0 | Edge measuring area Left: any value in measurement |
| 1 | range |
| 2 | (0.01µm unit Sined 32-bit integer |
| 3 | example: 5mm=500000) |
| 4 | Edge measuring area Right: any value in |
| 5 | measurement range |
| 6 | (0.01µm unit Sined 32-bit integer |
| 7 | example: 5mm=500000) |
| 8 | Edge direction: 0:Rising, 1:Falling |
| 9 | Detect direction: 0: +direction, 1: -direction |
| 10 | Detect No: 1~10 |
| 11 | Reserved(fixed as 0) |
| 12 | Edge lovel: any value in measurement range |
| 13 | Edge level: any value in measurement range (0.01µm unit Sined 32-bit integer |
| 14 | example: 5mm=500000) |
| 15 | coample. Jillii—Joodoo |

•9.2.3.12 Examples of sending/receiving measurement

mode settings

Example: When "Height (profile compression (time axis):

OFF" is selected and "Average" height is measured.

<Measurement mode>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:06h, Item:03h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data | |
|------|---|--|
| 0 | Minimum display unit(from①) | |
| 1 | Measurement mode(from②) | |
| 2 | Reserved(fixed as 0) | |
| 3 | Reserved(fixed as 0) | |
| 4 | From 4byte, unique parameters are assigned to | |
| ~ | each measurement mode. For details on the | |
| N | unique parameters, see [Unique parameters of | |
| N | measurement mode from 4byte] | |

1: Height (when profile compression(time axis) is off)

| byte | Setting Data | |
|------|---|---|
| 4 | Measurement target head: 0: HeadA, 1: HeadB, | |
| | 2: Combined profile(only when profile | |
| | combine(wide) is on) | |
| | Measurement target selection: 0: Peak, 1: | |
| 5 | Bottom, 2: Knee, 3: Intsect(lines), 4: | |
| | Intsect(lin-arc), 5: Center of circle, 6: Average | |
| | Position correction selection: 0: No position | |
| 6 | correction, 1: Position correction1, 2: Position | |
| | correction2 | |
| 7 | Reserved(fixed as 0) | |
| 8 | Unique parameters are assigned to each | |
| ~ | measurement target. For details on the unique | 4 |
| Z | parameters, see 9.2.3.11 "Measurement | |
| IN | Area"(page-41). | |
| N+1 | | |
| ~ | Reserved(fixed as 0) | |
| 91 | | |
| 6:A | /erage | • |

6:Average

| | . o. ago | _ |
|------|---|---|
| byte | Setting Data | |
| 0 | Area Left: any value in measurement range | ר |
| 1 | (0.01µm unit Sined 32-bit integer | |
| 2 | example: 5mm=500000) | |
| 3 | | |
| 4 | Acces Diable accession in management access | |
| 5 | Area Right: any value in measurement range | |
| 6 | (0.01µm unit Sined 32-bit integer | |
| 7 | example: 5mm=500000) | |

These can be summarized as follows:

<Measurement mode>

Type:10h~1Fh(10h:Program NO.0, 11h:Program

NO.1、···、1F:Program NO.15)

Category:06h, Item:03h

Target1:00h~0Fh(OUT1~16) Target2~4:00h

| byte | Setting Data | | |
|--------------------------------|--|--|--|
| 0 | Minimum display unit(from①) | | |
| 1 | Measurement mode (from②) | | |
| 2 | Reserved(fixed as 0) | | |
| 3 | Reserved(fixed as 0) | | |
| 4 | Measurement target head: 0: HeadA, 1: HeadB, 2: Combined profile(only when profile combine(wide) is on) | | |
| 5 | Measurement target selection: 0: Peak, 1: Bottom, 2: Knee, 3: Intsect(lines), 4: Intsect(lin-arc), 5: Center of circle, 6: Average | | |
| 6 | Position correction selection: 0: No position correction, 1: Position correction1, 2: Position correction2 | | |
| | | | |
| 7 | Reserved(fixed as 0) | | |
| 7 8 | | | |
| | Area Left: any value in measurement range | | |
| 8 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer | | |
| 8 | Area Left: any value in measurement range | | |
| 8 9 10 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) | | |
| 8 9 10 11 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) Area Right: any value in measurement range | | |
| 8 9 10 11 12 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) Area Right: any value in measurement range (0.01µm unit Sined 32-bit integer | | |
| 8 9 10 11 12 13 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) Area Right: any value in measurement range | | |
| 8 9 10 11 12 13 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) Area Right: any value in measurement range (0.01µm unit Sined 32-bit integer | | |
| 8 9 10 11 12 13 14 15 | Area Left: any value in measurement range (0.01µm unit Sined 32-bit integer example: 5mm=500000) Area Right: any value in measurement range (0.01µm unit Sined 32-bit integer | | |

Measurement mode 1:Height

Measurement target 6:Average

9.3 Writeing processing for settings

The following four VIs are used when a write operation is carried out for settings.

- · Set Setting
- · Reflect Setting
- · Update Write Settings Area
- · Check Status of Saving to Save Area

To send settings, it is necessary to specify the **Setting Depth** using **Set Setting**VI. Details on the **Setting Depth** option and its role are as follows:

| Depth option and its role are as follows. | | |
|---|--|--|
| Setting Depth | Role | |
| WRITE AREA | Settings written into this area will not be reflected in the controller. Setting written into this area will be reflected in RUNNING AREA or SAVE AREA by Reflect Setting VI. | |
| Settings written into this area will be reflected in the controller, be settings will not be saved when the power is turned off. (When it is rest settings will be reflected in SAVE AREA.) | | |
| SAVE AREA | Settings written into this area will be reflected in the controller. Even when the power is turned off, the settings are saved in the controller. However, it takes time to write into this area. (Check whether writing into this area is in progress using Check Status of Saving to Save Area VI. Verify that writing is finished from Saving to Save Area VI before turning off the power.) | |

<Usage example (1)> · · · When changing multiple settings in a batch

1 : Set Setting VI (WRITE AREA)

2 : Set Setting VI (WRITE AREA)

:

Final: Set Setting VI (WRITE AREA)

Reflect Setting VI (RUNNING AREA)

Consistency of settings is checked when writing into the RUNNING AREA or SAVE AREA. An error message is returned if any inconsistencies are found. (Errors can be checked by Context help.) If multiple settings are changed, therefore, when each setting is written into the RUNNING AREA (SAVE AREA), inconsistencies may occur due to the setting items, and the settings will not be reflected in the controller. Write multiple settings into the WRITE AREA, create consistent settings, and finally reflect them collectively in the controller.

To return inconsistent settings in the WRITE AREA to the settings within the controller, use **Update Write Settings Area** VI.

Note

- · Measurement is suspended when settings are written into RUNNING AREA (SAVE AREA).
- Do not turn off the power to the controller while settings are being written into SAVE AREA. You can check whether settings are being written using **Check Status of Saving to Save Area** VI.
- If the last **Set Setting** VI (WRITE AREA) is used as **Set Setting** VI (RUNNING), the same results can be obtained. (It is then not necessary to update WRITE AREA.)

<Usage example (2)>··· When only one setting is changed

· When settings are not saved to the controller

Set Setting VI (RUNNING AREA)

· When settings are saved to the controller

Set Setting VI (SAVE AREA)

Note

- · Measurement is suspended when settings are written into RUNNING AREA (SAVE AREA).
- Do not turn off the power to the controller while settings are being written into SAVE AREA. You can check whether settings are being written using **Check Status of Saving to Save Area** VI.

10. Appendix

10.1 Internal memory of controller

When using the following VIs, it is necessary to specify a memory area within the controller that reads data. To specify the memory area, use **Read Area** of **Read Req** input. When data is read only from the internal memory where data is currently being stored, specify **Read Area**: 0.

- · Read Profiles (for High-Speed Mode)
- · Read Batch Profiles (for High-Speed Mode)
- · Read Storage Status
- · Read Data Storage Data
- · Read Profile Storage Data
- · Read Batch Profile Storage Data

When an internal memory within the controller is used by allocating to a double buffer, etc., the method for specifying **Read Area** varies depending on "Memory Allocation" and "Operating Mode". (For information on allocation of the internal memory, refer to 9-5 in the LJ-V7000 Series User's Manual.)

| Memory Allocation | | Operating Mode | Read Area |
|----------------------------------|---|-------------------|---|
| Double Buffer | Divides an internal memory into two surfaces - Surface A and Surface B. Alternates between using Surface A and Surface B every time a program is changed. The surface on which data is currently being stored is called the active surface. | High speed | Active surface: TRUE, Inactive surface: FALSE |
| | A:1 B:2 | Advanced | Active surface: 0, Surface A: 1, Surface B: 2 |
| | Uses the entire area of the internal memory. | High speed | Specify TRUE. |
| Entire area (Overwrite) | 1 | Advanced | Specify 1. |
| Entire area (No overwrite) | The area within the entire internal memory area where data is not stored. 1 2 3 4 Storing | Advanced | Every time a program is changed, the Read Area counts up 1→2→3···. Enter 1 - 1000 depending on the area you want to read. To read the area that is currently being used for storage, enter 0.(*1) * No additional data can be stored when the program change number exceeds 1000. |

* 1 For the Read Area where data is being stored, call Read Storage Status VI and check the Active Surface of Storage Status Rsp output.

Note

- When reading a profile, if the profile is read by specifying TRUE for Erase of the Read Req input (the
 read profile is erased), the read profile (batch) and other profiles older than this (batch) will be deleted
 from memory.
- •When the controller sends the read profile during high speed data communication, the sent profile will be deleted from memory.
- When profiles are continuously read from the controller, if the PC reads and deletes the profiles at a speed slower than the speed at which data is saved to the controller, the memory will become full. Data to be read after the current profile or data read before the current profile will be deleted as dictated in the settings for operations when the memory is FULL. (For more information, refer to 9-5 in the LJ-V7000 Series User's Manual.)

10.2 Profile data amount calculation method

The amount of profile data to get is a value multiplied by a correction factor determined from the settings below with 800 as the base.

| | Setting | | Correction | |
|------------------|------------------------------|---------------|------------|---------------|
| Category | Item | Setting value | factor | Comment |
| | Measurementrange X direction | FULL | 1.00 | Initial value |
| Imaging | | MIDDLE | 0.75 | |
| Imaging settings | | SMALL | 0.50 | |
| Settings | Binning | OFF | 1.00 | Initial value |
| | | ON | 0.50 | |
| | Combine (wide) | OFF | 1.00 | Initial value |
| | | ON | 2.00 | |
| Profile settings | Compression (X axis) | OFF | 1.00 | Initial value |
| | | 2 | 0.50 | |
| | | 4 | 0.25 | |

For example, the amount of profile data with the settings below is $300 = 800 \times 0.75 \times 1.00 \times 1.00 \times 0.50$ items of data.

Measurement range X direction: Middle, Binning: Off, Combine (wide): Off, Compression (X axis): 2

However, when the amount of profile data found as a result of the equation above is less than 200, the profile compression (X axis) setting is adjusted so that the amount of profile data is 200 or higher. For example, in a situation like that below, the amount of profile data is 300.

Measurement range X direction: Middle, Binning: Off, Combine (wide): Off, Compression (X axis): 4. The specific calculation is described below.

- 1. $800 \times 0.75 \times 1.00 \times 1.00 \times 0.25 = 150$
- 2. The result is less than 200, so the profile compression (X axis) setting is adjust to 2 instead of 4
- 3. $800 \times 0.75 \times 1.00 \times 1.00 \times 0.5 = 300$
- 4. The result is 200 or higher, so the amount of profile data above is confirmed

10.3 Profile data storage order and Specific examples

In functions that get profile data, such as **Read Profiles(for High-Speed Data Communication)** VI, the profile data stored in the area between header and footer is 1 unit of profile data found with 10.2 "Profile data amount calculation method", and the data is stored in the order below.

- Storage order
 - 1. 1st head profiles (when compression (time axis) is on, MAX profiles)
 - 2. 1st head MIN profiles
 - 3. 2nd head profiles (when compression (time axis) is on, MAX profiles)
 - 4. 2nd head MIN profiles
- Notes

3 and 4 only exist when the number of heads is 2 and wide is off.

2 and 4 only exist when compression (time axis) is on.

- Specific examples
- (i) For configuration 1 (initial settings)

Heads: 2, Measurement range X direction: Full, Binning: Off, Wide: Off, Compression (X axis): Off, Compression (time axis): Off

The amount of profile data is 800

The profile data storage order is as follows. (See profile data storage order for 1)

- 1. Head A profiles (800)
- 3. Head B profiles (800)

When getting 10 profiles with Read Profiles VI, the data below is stored in ProfileData.

| Profile1 | header*1 | 32bit×6 |
|-----------|--------------------------|-----------|
| | 1. Head A profiles (800) | 32bit×800 |
| | 3. Head B profiles (800) | 32bit×800 |
| | footer | 32bit×1 |
| | : | |
| Profile10 | header*1 | 32bit×6 |
| | 1. Head A profiles (800) | 32bit×800 |
| | 3. Head B profiles (800) | 32bit×800 |
| | footer | 32bit×1 |

^{*} For header details, refer to 10.4.

(ii) For configuration 2

Heads: 2, Measurement range X direction: Full, Binning: on, Wide: off, Compression (X axis): 2,

Compression (time axis): On

The amount of profile data is 200

The profile data storage order is as follows. (See profile data storage order for 1)

- 1. Head A MAX profiles (200)
- 2. Head A MIN profiles (200)
- 3. Head B MAX profiles (200)
- 4. Head B MIN profiles (200)

*Profile data(32bit×800)

When getting 10 profiles with Read Profiles VI, the data below is stored in ProfileData.

| Profile1 | header*1 | 32bit×6 |
|-----------|---------------|-----------|
| | *Profile data | 32bit×800 |
| | footer | 32bit×1 |
| | : | |
| Profile10 | header*1 | 32bit×6 |
| | *Profile data | 32bit×800 |
| | footer | 32bit×1 |

^{*}see the detail of header at 10.4.

10.4 Header Details (Encoder Counter/Z-phase Flag/Trigger Counter)

The section below contains details of 32 bit x 6 headers.

| Coolin Solow Contains Grant of CL Six X o Headerer | | | | |
|--|--|---------|--|--|
| header | 7th bit: Indicates whether the encoder's Z | 32bit | | |
| | phase has been entered. (*) | | | |
| | MSB ↓ LSB | | | |
| | 31 7 6 5 4 3 2 1 0 | | | |
| | | | | |
| | Indicates which number trigger from the start of | 32bit | | |
| | measurements this profile is. (Trigger counter) | | | |
| | The encoder count when the trigger was | 32bit | | |
| | issued. (Encoder counter) | | | |
| | reserve | 32bit×3 | | |


Other than when settings are modified or the program is switched, the trigger counter and the encoder counter are reset at the following times.

- When the memory is cleared in high-speed mode (profile only)
- · When laser emission stops and is restarted with the LASER_OFF terminal
- When laser emission is allowed after it was prohibited with the REMOTE terminal
- * About the Z-phase flag


This flag can be used when the controller is version 3.0 or later.

This flag is turned ON when Z-phase ON input is received during the period between the previous trigger input (or the start of measurement if there was no previous trigger input) and the current trigger input.

Example: Single phase 1x multiplier encoder trigger with no skipping



Note: When the Z-phase input uses a negative logic encoder, set the TRG minimum input time, which is a common measurement setting, to 7 μ s. With negative logic, the Z-phase flag turns ON as shown in the following figure.




10.5 Storage Order of Profile Storage Data and Specific Examples

Read Profile Storage Data VI allows you to read stored profile data, measurement values and internal measurement values (*1). Data to be read has the following structure when 1 line = 1 byte settings are configured.

*1 "Internal measurement value" means the measurement value immediately before the measurement mode processing of the OUT measurement setting is performed. There is one internal measurement value of each OUT for each piece of profile data.

Structure of one piece of profile storage data



^{*} Result of determining tolerance of internal measurement values is always 0.

10.6 Storage Order of Batch Profile Storage Data and Specific Examples

Read Profile Storage Data VI allows you to read stored profile data and measurement values. Data to be read has the following structure. Data to be read has the following structure when 1 line = 1 byte settings are configured.

Structure of one piece of batch profile storage data 22 23 24 when profile count is 800 *Profile count depends on the setting. See 10.2 Profile data amount calculation method. 3223 3224 3225 3226 3227 3228 Measure data(OUT1) 3229 Judgment result reserve 3230 3231 reserve 3232 3233 3234 3235 Internal measurement value Measure data(OUT16) 3348 Measurement data information (Example: Measurement values for 3349 Judgment result profile. Measurement value directly 3350 reserve 3351 reserve before measurement mode 3352 Measurement value processing is performed.) 3353 3354 3355

10.7 Storage Order of Data Storage Data and Specific Examples

Read Data Storage Data VI allows you to read stores measurement values. Data to be read has the following structure.

Structure of one piece of data storage data Storage time Measurement data information Measure data(OUT1) Judgment result reserve Measurement value 124 Measure data(OUT16) Measurement data information 125 Judgment result reserve 127 reserve 128 Measurement value 129 130 131

^{*} Result of determining tolerance of internal measurement values is always 0.